

Physic Break Out 3D Documentation

Overview

The **Physic Break Out 3D** project is thoughtfully developed and user-friendly. Function names are clear, and scripts provide step-by-step guidance. This documentation explains the project folders functions. If you encounter any issues, please contact us at blackrosedevelopers@gmail.com.

Project Structure

1. Art

Art folder is subdivided into three folders.

A. Materials

Contains 12 various materials used in the game, which can be customized with different colours or textures.

B. Models:

Contains 14 3D unique models (FBX)

C. Textures:

Contains 12 textures that can be applied to materials (PNG)

2. Prefabs

The Prefabs folder has 38 prefabs that can be used throughout the gameplay ranging from balls to blocks.

3. Scenes

- **SampleScene**: this is the main scene of the game

4. Scriptable Objects

- **Data Storage**: Main storage of game data (number of levels and unlocked ones)


5. Scripts

15 Scripts with clear names and functions to ensure easy understanding.


How to add new levels:

Levels should be designed in 3D scenes


- 1- Navigate to Project – Scenes folder. Double click on SampleScene.scene




- 2- There are 7 levels already in the game. Find Game Control game object in the scene and Level prefabs variable.




- 3- In order to add new levels to the game, navigate to Prefabs – Levels folder and copy one of the 1 to 7 levels and start changing it. for this example, I chose level 7 and after duplicating, I rename to level-8.



4- You can set different prefabs in your level from Prefabs folder.
Here I decided to blocks, dummy blocks, multiply and speed.



5- After you are done with level designing, add your new prefab of level to Game Control Object.




6- The last step is to update your win ui script and increment level number.

```
0 references
public void BtnContinue()
{
    m_DataStorage.m_LevelNum++;
    if (m_DataStorage.m_LevelNum > 7)
    {
        m_DataStorage.m_LevelNum = 0;
    }

    SceneManager.LoadScene(SceneManager.GetActiveScene().name);
}
```

7- If you intent to test the level, change data storage (Level Num).



For any questions or further assistance, please reach out to blackrosedevelopers@gmail.com.