

WARP Crossdock App v3.0 SOP

Effective Date: 5/22/2025

Prepared By: Brandon Wood

Department: Facility Operations

1. Purpose

This SOP outlines how to use the WARP Crossdock App v2.0 for inbound and outbound processing at WARP crossdock facilities, including scanning procedures, shipment identification, incident reporting, and support features such as the "Help Driver Pickup" tool.

2. Scope

Applicable to all WARP crossdock staff responsible for inbound and outbound shipment handling using the Crossdock App.

3. App Overview

After logging in, the Home Screen displays three tabs:

- **Inbound:** Lists today's pending inbound routes
- **Outbound:** Lists today's pending outbound routes
- **Settings:** Adjust user profile, preferences, or log out of the app

Both Inbound and Outbound tabs update in real time as routes are created, checked in, or checked out. By end of day, both lists should be empty.

4. Inbound Processing

4.1 Identify Route

You can identify a route using one of the following:

- **WARP Load Tender:** Scan the QR code at the bottom of the document.
- **WARP Bill of Lading (BOL):** Scan the QR code at the bottom of the BOL.
- **WARP Route ID:** Manually enter the Route ID (e.g., 1234-2444) in the search bar.

4.2 Route Detail Screen

Displays:

- Carrier and driver info
- Shipments and pallet tasks (scan, photo, weight)
- Toggle to view completed tasks
- Shipment ID, leg ID, reference numbers, order ID, customer name, and next destination

4.3 Identify Shipment

Scan QR code on the Shipment BOL or search by shipment ID, PRO number, or reference number.

4.4 Identify Item

Scan pallet labels (provided or previously applied). Pallets with barcodes are auto-marked as checked in.

4.5 Assign Pallet Labels

1. Identify the shipment
2. Tap **Assign Barcode**
3. Scan and assign labels
4. Tap **Confirm** to assign and auto-check-in the pallets

5. Incident Reporting & Exceptions

5.1 Report Damage

1. Go to the shipment detail screen
2. Tap the 3-dot menu
3. Select **Report Damage**
4. Take photos and input damaged pallet count

5.2 Update Pallet Count

1. Tap 3-dot menu > **Update Pallet Count**
2. Use + or – to adjust quantity

Note: Count cannot go below the number of labeled pallets

5.3 Report Missing Pallet

1. Tap the 3-dot menu next to the pallet
2. Select **Report Missing**
3. Confirm — pallet is removed from shipment and tasks cleared

6. Outbound Processing

6.1 Identify Route

Scan a pallet from the Outbound screen — this does **not** mark it as checked out. The user must proceed to complete checkout manually.

6.2 Scan & Checkout

1. Use **Bulk Scan Out** on the shipment or route detail screen
 2. Shipments are listed in **reverse delivery order** (load last deliveries first)
 3. View pallet photos to aid in loading
 4. After all pallets are scanned, tap **Complete** to finalize route checkout
-

7. Help Driver Pickup Feature

7.1 Overview

This feature is used when a driver is unable to scan pallets during pickup. This may occur due to sealed pallets on linehaul routes or device/labeling issues. In these situations, warehouse operators must assist in verifying pickup.

7.2 Instructions

1. The driver app will prompt the driver to request assistance.
2. The warehouse operator opens their Crossdock App.
3. Search for the driver's route by entering the **Route ID**.
4. Use the **Release** button to confirm pickup of each pallet.

This ensures correct pallets are released and recorded.

8. New WARPID Format

A new WARPID format (S-XXXX-XXXX) has replaced the old format (S-XXXXX).

- Effective **June 1, 2025**, the old WARPID format will no longer appear on BOLs.
- Warehouse operators should begin using the new format immediately to ensure consistency across all documentation and systems.

