

Cluster

Get-Cluster Move-Cluster New-Cluster Remove-Cluster Set-Cluster Get-DrsClusterGroup New-DrsClusterGroup Remove-DrsClusterGroup Set-DrsClusterGroup Get-DrsRecommendation Invoke-DrsRecommendation Get-DrsRule New-DrsRule Remove-DrsRule Set-DrsRule Get-DrsVMHostRule New-DrsVMHostRule Remove-DrsVMHostRule Set-DrsVMHostRule Get-HAPrimaryVMHost Get-ResourcePool Move-ResourcePool New-ResourcePool

Remove-ResourcePool

Set-ResourcePool

Get-AdvancedSetting New-AdvancedSetting Remove-AdvancedSetting Set-AdvancedSetting

Get-AlarmAction New-AlarmAction Remove-AlarmAction Get-AlarmActionTrigger New-AlarmActionTrigger Remove-AlarmActionTrigger Get-AlarmDefinition Set-AlarmDefinition Get-Annotation Set-Annotation Get-ContentLibraryItem Get-CustomAttribute New-CustomAttribute Remove-CustomAttribute Set-CustomAttribute Get-Datacenter Move-Datacenter New-Datacenter Remove-Datacenter Set-Datacenter Get-ErrorReport Get-Folder Move-Folder

vCenter Server Get-Inventory Move-Inventory Remove-Inventory Get-OSCustomizationNicMapping New-OSCustomizationNicMapping Remove-OSCustomizationNicMapping Set-OSCustomizationNicMapping Remove-OSCustomizationSpec

Get-OSCustomizationSpec New-OSCustomizationSpec Set-OSCustomizationSpec Get-OvfConfiguration Get-Stat Get-StatInterval New-StatInterval Remove-StatInterval Set-StatInterval Get-StatType Get-Tag New-Tag Remove-Tag Set-Tag Get-TagAssignment New-TagAssignment Remove-TagAssignment **Get-TagCategory** New-TagCategory Remove-TagCategory Set-TagCategory

Stop-Task

Wait-Task

Get-VApp

Export-VApp

Import-VApp

Move-VApp

New-VApp

Set-VApp

Start-VApp

Stop-VApp

Get-VIEvent

Get-VIAccount

New-VIInventoryDrive

Get-VIObjectByVIView

Remove-VIPermission

Get-VIPermission

New-VIPermission

Set-VIPermission

Get-VIPrivilege

Get-VIProperty

Get-VIRole

New-VIRole

Set-VIRole

Remove-VIRole

Connect-VIServer

Get-VMHostProfile

Import-VMHostProfile

Invoke-VMHostProfile

Remove-VMHostProfile

Test-VMHostProfileCompliance

New-VMHostProfile

Set-VMHostProfile

Disconnect-VIServer

New-VIProperty

Remove-VIProperty

Remove-VApp

Get-CDDrive New-CDDrive Remove-CDDrive Set-CDDrive Get-FloppyDrive New-FloppyDrive Remove-FloppyDrive Set-FloppyDrive Copy-HardDisk Get-HardDisk Move-HardDisk New-HardDisk Remove-HardDisk Set-HardDisk Get-NetworkAdapter New-NetworkAdapter Remove-NetworkAdapter Set-NetworkAdapter Add-PassthroughDevice Get-PassthroughDevice Remove-PassthroughDevice Get-ScsiController New-ScsiController Set-ScsiController Get-Snapshot New-Snapshot Remove-Snapshot Set-Snapshot

Get-Template

Set-Template

Mount-Tools Update-Tools

Wait-Tools

Get-VM

Move-VM

New-VM

Set-VM

Start-VM

Stop-VM

Suspend-VM

Remove-VM

Restart-VM

Dismount-Tools

Get-UsbDevice

Remove-UsbDevice

Move-Template New-Template Remove-Template

NSX-T Common Infrastructure Connect-NsxtServer Get-CisCommand Disconnect-NsxtServer Get-NsxtService Connect-CisServer Disconnect-CisServer Get-CisService

Nsxt

Sdk

Storage

Get-PowerCLIConfiguration Set-PowerCLIConfiguration Get-PowerCLIVersion Get-VICommand Get-VICredentialStoreItem New-VICredentialStoreItem *

Remove-VICredentialStoreItem

VMware PowerCLI Modules

Vds

Vmc

Common

Stop-CIVAppGuest

Get-CIVAppNetwork

New-CIVAppNetwork

Set-CIVAppNetwork

Get-CIVAppStartRule

Restart-CIVMGuest

Get-Baseline

Remove-Baseline

Get-Compliance

Test-Compliance

Add-EntityBaseline

Get-PatchBaseline

New-PatchBaseline

Set-PatchBaseline

Get-VumCommand

vSphere Licensing

Get-LicenseDataManager

Get-LicensingCommand

Remove-EntityBaseline

Update-Entity

Copy-Patch

Get-Patch

Sync-Patch

vSphere Update Manager

Remove-CIVAppNetwork

Deploy

HorizonView

Get-CloudCommand

Get-ExternalNetwork

Get-NetworkPool

Get-Media

Get-Org

New-Org

Set-Org

Remove-Org

Automation

PowerCLI

Connect-Vmc Disconnect-Vmc Get-VmcService

ImageBuilder

License

PCloud

VMware Cloud on AWS

Update-VmfsDatastore

vROps

VumAutomation

Cloud

Switch-ActiveDeployRuleSet

Get-AutoDeployCommand

Export-AutoDeployState

Import-AutoDeployState

Repair-DeployImageCache

Get-DeployMachineIdentity

Set-DeployMachineIdentity

Get-DeployOption

Set-DeployOption

Copy-DeployRule

Add-DeployRule

Get-DeployRule

New-DeployRule

Set-DeployRule

Remove-DeployRule

Get-DeployRuleSet

Set-DeployRuleSet

Add-ProxyServer

Get-ProxyServer

Add-ScriptBundle

Get-ScriptBundle

Remove-ProxyServer

Get-VMHostAttributes

Get-VMHostImageProfile

Get-VMHostMatchingRules

Get-PIComputeInstance

Get-PIDatacenter

Connect-PIServer

Disconnect-PIServer

vCloud Air

Repair-DeployRuleSetCompliance

Test-DeployRuleSetCompliance

Set-ESXImageProfileAssociation

vSphere Auto Deploy

- Internet Connectivity MacOS/Linux Prerequisites:

Windows Prerequisites:

- PowerShell Core 6.0.1+

directly from within PowerShell

- Internet Connectivity

Installation:

- Open a PowerShell Session - Run: Install-Module VMware.PowerCLI -Scope CurrentUser

Connect to vCenter Server or ESXi

Installing PowerCLI

Installation of PowerCLI is from the PowerShell Gallery and is done

- PowerShell 5.x (OR manually install PowerShellGet)

- Uninstall PowerCLI 6.5 R1 (OR any other previous versions)

To connect to a VMware vCenter server or ESXi Host: Start a new PowerShell Session \$srv = Connect-VIServer -Server "vcenter.fadn" -User Admin -Password Pass01

To disconnect from the connected vSphere server: **Disconnect-VIServer** -Server \$srv -Confirm:\$false

Getting Started Samples

To list all the snapshots for all virtual machines: **Get-VM** | **Get-Snapshot**

Get-VsanDisk -VsanDiskGroup \$vsanDiskGroup

Top 5 VM memory allocation: Get-VM | Sort-Object -Property MemoryGB -Descending | Select -First 5

Total memory available on all ESXi: Get-VMHost | Measure-Object -Property MemoryTotalGB -Sum | **Select** -ExpandProperty Sum

To list all the port groups and some of their properties: \$vs = Get-VirtualSwitch -VMHost "vmhost.fqdn" -Name "Switch01"

Get-VirtualPortGroup -VirtualSwitch \$vs To list all of the disks within a VSAN disk group for an ESXi host \$vsanDiskGroup = Get-VsanDiskGroup -VMHost "vmhost.fqdn"

Remotely Invoke Commands Invoke-VMScript -VM "LABTEST1" -ScriptText "dir" -GU Administrator

Community Repository

The VMware PowerCLI Community Repository is a central location where anyone can contribute their own resources. The repository features a Principles of Operations document to help guide contributors along the process of using, creating, and updating resources which are contained within the repository.

Link: https://github.com/vmware/PowerCLI-Example-Scripts

Featured Scripts:

Home Lab Deployment

Featured Modules:

- VMware on AWS

- Horizon View Helper

- Affinity Rule Creation - LUN Path Report - VM Encryption

Additional Resources

Official PowerCLI Blog - http://blogs.vmware.com/PowerCLI/ Documentation - https://code.vmware.com/tool/vmware-powercli VMware PowerCLI Community - http://vmware.com/go/powercli

Twitter - https://twitter.com/PowerCLI LinkedIn - http://www.linkedin.com/groups/PowerCLI-Users-162324

Facebook - https://www.facebook.com/vmwarepowercli Slack - https://code.vmware.com/web/code/join

https://mylearn.vmware.com/mgrreg/courses.cfm?a=one&id_subject=71972

Third-Party PowerCLI training from Pluralsight - http://www.pluralsight.com

ESXi Host

New-Folder

Set-Folder

Remove-Folder

Get-Datastore Move-Datastore New-Datastore Remove-Datastore Set-Datastore Get-DatastoreCluster New-DatastoreCluster Remove-DatastoreCluster Set-DatastoreCluster New-DatastoreDrive Copy-DatastoreItem Get-EsxCli

Get-EsxTop Get-IScsiHbaTarget New-IScsiHbaTarget Remove-IScsiHbaTarget Set-IScsiHbaTarget Get-Log Get-LogType Get-NicTeamingPolicy Set-NicTeamingPolicy Get-ScsiLun Set-ScsiLun Get-ScsiLunPath Set-ScsiLunPath

Get-SecurityPolicy

Set-SecurityPolicy

Get-VirtualPortGroup

New-VirtualPortGroup Remove-VirtualPortGroup Set-VirtualPortGroup Get-VirtualSwitch New-VirtualSwitch Remove-VirtualSwitch Set-VirtualSwitch Add-VirtualSwitchPhysicalNetworkAdapter Add-VMHost Get-VMHost

emove-VirtualSwitchPhysicalNetworkAdapter Move-VMHost Remove-VMHost Restart-VMHost Start-VMHost Stop-VMHost Suspend-VMHost Get-VMHostAccount New-VMHostAccount Remove-VMHostAccount Set-VMHostAccount Get-VMHostAdvancedConfiguration Set-VMHostAdvancedConfiguration Get-VMHostAuthentication Set-VMHostAuthentication

Get-VMHostAvailableTimeZone

Get-VMHostDiagnosticPartition

Get-VMHostDisk Format-VMHostDiskPartition Get-VMHostDiskPartition Get-VMHostFirewallDefaultPolicy Set-VMHostFirewallDefaultPolicy Get-VMHostFirewallException Set-VMHostFirewallException Get-VMHostFirmware Set-VMHostFirmware Get-VMHostHardware * Get-VMHostHba

Set-VMHostDiagnosticPartition

Set-VMHostHba Get-VMHostModule Set-VMHostModule Get-VMHostNetwork Set-VMHostNetwork Get-VMHostNetworkAdapter New-VMHostNetworkAdapter Remove-VMHostNetworkAdapter Set-VMHostNetworkAdapter Add-VMHostNtpServer Get-VMHostNtpServer Remove-VMHostNtpServer Get-VMHostPatch Install-VMHostPatch Get-VMHostPciDevice Export-VMHostProfile Get-VMHostProfileRequiredInput Get-VMHostRoute New-VMHostRoute Remove-VMHostRoute Set-VMHostRoute Get-VMHostService Restart-VMHostService Start-VMHostService Stop-VMHostService Get-VMHostSnmp Set-VMHostSnmp Test-VMHostSnmp Get-VMHostStartPolicy Set-VMHostStartPolicy Get-VMHostStorage Set-VMHostStorage

Get-VMHostSysLogServer

Set-VMHostSysLogServer

vSAN

Stop-VMGuest

Get-VMGuest

Open-VMConsoleWindow

Suspend-VMGuest Copy-VMGuestFile Get-VMQuestion Set-VMQuestion Get-VMResourceConfiguration Set-VMResourceConfiguration Invoke-VMScript Get-VMStartPolicy

Set-VMStartPolicy

etAssociation

Get-Catalog

Get-ClUser

Get-CIVApp

New-CIVApp

Set-CIVApp

Start-CIVApp

Stop-CIVApp

Get-OMAlert

Set-OMAlert

Suspend-CIVApp

Restart-CIVAppGuest

Get-OMAlertDefinition

Get-OMAlertSubType

Get-OMRecommendation

Get-OMAlertType

Get-OMResource

Get-OMStat

Get-OMUser

Get-OMStatKey

Connect-OMServer

Disconnect-OMServer

Get-vROpsCommand

Get-HvCommand

Connect-HVServer

Disconnect-HVServer

Horizon View

vRealize Operations Manager

Import-CIVApp

Remove-CIVApp

Restart-CIVApp

Get-CIAccessControlRule New-CIAccessControlRule Remove-CIAccessControlRule Set-CIAccessControlRule Add-CIDatastore Get-CIDatastore Get-CINetworkAdapter Set-CINetworkAdapter Get-CIRole Connect-CIServer Disconnect-CIServer

Cis.Core

Core

StorageUtility

Set-CIVAppStartRule Get-CIVAppTemplate Import-CIVAppTemplate New-CIVAppTemplate Remove-CIVAppTemplate Set-CIVAppTemplate

vCloud Director

Get-OrgNetwork New-OrgNetwork Remove-OrgNetwork Set-OrgNetwork Get-CIView Get-OrgVdc New-OrgVdc Get-CIVM New-CIVM Remove-OrgVdc Restart-CIVM Set-OrgVdc Get-OrgVdcNetwork Start-CIVM Get-ProviderVdc Stop-CIVM Suspend-CIVM

Stop-CIVMGuest Get-CIVMTemplate Search-Cloud

Image Builder

Compare-EsxImageProfile Export-EsxImageProfile Get-EsxImageProfile New-EsxImageProfile Remove-EsxImageProfile Set-EsxImageProfile Add-EsxSoftwareDepot Get-EsxSoftwareDepot Add-EsxSoftwarePackage

Remove-EsxSoftwareDepot Get-EsxSoftwarePackage Remove-EsxSoftwarePackage Get-ImageBuilderCommand

SRM

Connect-SrmServer

Disconnect-SrmServer

High Availability

vSphere Distributed Switch

Get-VDBlockedPolicy Set-VDBlockedPolicy Get-VDPort Set-VDPort Export-VDPortGroup Get-VDPortgroup New-VDPortgroup Remove-VDPortGroup Set-VDPortgroup Get-VDPortgroupOverridePolicy Set-VDPortgroupOverridePolicy Get-VDSecurityPolicy Set-VDSecurityPolicy **Export-VDSwitch** Get-VDSwitch New-VDSwitch Remove-VDSwitch Set-VDSwitch Add-VDSwitchPhysicalNetworkAdapter Remove-VDSwitchPhysicalNetworkAdapter Get-VDSwitchPrivateVlan New-VDSwitchPrivateVlan Remove-VDSwitchPrivateVlan Add-VDSwitchVMHost Remove-VDSwitchVMHost Get-VDTrafficShapingPolicy

Set-VDTrafficShapingPolicy

Get-VDUplinkTeamingPolicy

Set-VDUplinkTeamingPolicy

Set-VDVlanConfiguration

Get-VDUplinkLacpPolicy

Set-VDUplinkLacpPolicy

Get-KeyManagementServer Remove-KeyManagementServer Set-KeyManagementServer Get-KmipClientCertificate New-KmipClientCertificate Get-KmsCluster Set-KmsCluster Get-NfsUser New-NfsUser Remove-NfsUser Set-NfsUser Get-SpbmCapability Get-SpbmCompatibleStorage Get-SpbmEntityConfiguration Set-SpbmEntityConfiguration Get-SpbmFaultDomain Get-SpbmPointInTimeReplica

Storage

Start-SpbmReplicationFailover Get-SpbmReplicationGroup Sync-SpbmReplicationGroup Get-SpbmReplicationPair Start-SpbmReplicationPrepareFailover Start-SpbmReplicationPromote Start-SpbmReplicationReverse Start-SpbmReplicationTestFailover Stop-SpbmReplicationTestFailover New-SpbmRule New-SpbmRuleSet Export-SpbmStoragePolicy Get-SpbmStoragePolicy

Import-SpbmStoragePolicy

New-SpbmStoragePolicy

Add-KeyManagementServer Remove-SpbmStoragePolicy Set-SpbmStoragePolicy Get-VAIOFilter New-VAIOFilter

Remove-VAIOFilter Set-VAIOFilter Get-VasaProvider New-VasaProvider Remove-VasaProvider Get-VasaStorageArray Copy-VDisk Get-VDisk Move-VDisk New-VDisk Remove-VDisk Set-VDisk

Test-VsanClusterHealth Start-VsanClusterRebalance Stop-VsanClusterRebalance Start-VsanEncryptionConfiguration

* = Unsupported on MacOS, Linux

Get-VsanClusterConfiguration

Start-VsanClusterDiskUpdate

Set-VsanClusterConfiguration

Get-VsanDisk New-VsanDisk Remove-VsanDisk Get-VsanDiskGroup New-VsanDiskGroup Remove-VsanDiskGroup Get-VsanEvacuationPlan Get-VsanFaultDomain New-VsanFaultDomain Remove-VsanFaultDomain Set-VsanFaultDomain Update-VsanHclDatabase Get-VsanlscsilnitiatorGroup New-VsanIscsiInitiatorGroup Remove-VsanIscsiInitiatorGroup Set-VsanlscsilnitiatorGroup

etAssociation Remove-VsanIscsiInitiator-GroupTargetAssociation Get-VsanlscsiLun New-VsanIscsiLun Remove-VsanlscsiLun Set-VsanIscsiLun Get-VsanIscsiTarget New-VsanIscsiTarget Remove-VsanIscsiTarget Set-VsanIscsiTarget Test-VsanNetworkPerformance Repair-VsanObject Get-VsanResyncingComponent Get-VsanRuntimeInfo Get-VsanSpaceUsage Get-VsanStat Test-VsanStoragePerformance Get-VsanView Test-VsanVMCreation

Get-VsanlscsilnitiatorGroupTarg-

New-VsanlscsilnitiatorGroupTarg-

= Multiplatform Support including MacOS, Linux (PowerShell Core 6), = Windows Support,

f @VMwarePowerCLI

in @PowerCLI

VMware Education Course: Data Center Automation with vRealize Orchestrator and Get-DrmInfo

vSphere PowerCLI -