




workspace_1.9.0 - Device Configuration Tool - STM32CubeIDE

File Edit Navigate Search Project Run Window Help

Project Explorer HW22.ioc

HW22

- Includes
- Core
- Drivers
- HW22.ioc
- STM32F103C8TX_FLASH

HW22.ioc - Pinout & Configuration

Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs Pinout

A-Z

Categories

System...

DMA

GPIO

IWDG

NVIC

RCC

SYS

WWDG

Analog

Timers

Connect

Computi

Middlew

NVIC Mode and Configuration

Configuration

NVIC Code generation

Priority Group 4 bit... Sort by Preemption Priority and Sub Priority

Search Show available interrupts

NVIC Interrupt Table

	Enabled	
Non maskable interrupt	☒	0
Hard fault interrupt	☒	0
Memory management fault	☒	0
Prefetch fault, memory access fault	☒	0
Undefined instruction or illegal state	☒	0
System service call via SWI instruction	☒	0
Debug monitor	☒	0
Pendable request for system service	☒	0
Time base: System tick timer	☒	0
PVD interrupt through EXTI line 16	☐	0
Flash global interrupt	☐	0
RCC global interrupt	☐	0
TIM3 global interrupt	☒	0
I2C2 event interrupt	☐	0
I2C2 error interrupt	☐	0

☐ Enabled Preemption Priority

Pinout view System view

Pinout diagram of the STM32F103C8Tx LQFP48 package. The diagram shows the following connections:

- Top: VDD, VSS, PB9, PB8, BOOT0, PB7, PB6, PB5, PB4, PB3, PA15, PA14
- Left: VBAT, PC13, PC14, PC15, PD0-O, PD1-O, NRST, VSSA, VDDA, PA0, PA1, PA2
- Right: VDD, VSS, PA13, PA12, PA11, PA10, PA9, PA8, PB15, PB14, PB13, PB12
- Bottom: PA3, PA4, PA5, PA6, PA7, PB0, PB1, PB2, PB10, PB11, VSS, VDD

Additional components and labels include:

- RCC_OSC_IN, RCC_OSC_OUT
- I2C2_SCL, I2C2_SDA
- FAN
- button1, button2, button3

ENG 11:37:28

workspace_1.9.0 - Device Configuration Tool - STM32CubeIDE

File Edit Navigate Search Project Run Window Help

Project Explorer HW22 STM32F103C8TX_FLASH

HW22.ioc - Pinout & Configuration

Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

Pinout view System view

RCC Mode and Configuration

Mode

High Speed Clock (HSE) Crystal/Ceramic Resonator

Low Speed Clock (LSE) Disable

Master Clock Output

Configuration

Reset Configuration

NVIC Settings

GPIO Settings

Parameter Settings

User Constants

Configure the below parameters :

Search (Ctrl+F)

System Parameters

VDD voltage (V) 3.3 V

Prefetch Buffer Enabled

Flash Latency (WS) 0 WS (1 CPU cycle)

RCC Parameters

HSI Calibration Value 16

LSE Startup Time Value 400

STM32F103C8Tx LQFP48

Pinout diagram showing the STM32F103C8Tx LQFP48 package with pins labeled VDD, VSS, VBAT, PC13, PC14, PC15, PD0, PD1, NRST, VSSA, VDDA, PA0, PA1, PA2, PA3, PA4, PA5, PA6, PA7, PA8, PA9, PA10, PA11, PA12, PA13, PA14, PA15, PB0, PB1, PB2, PB3, PB4, PB5, PB6, PB7, PB8, PB9, PB10, PB11, PB12, PB13, PB14, PB15, VSS, VDD, and buttons labeled button1, button2, button3, and FAN.

workspace_1.9.0 - Device Configuration Tool - STM32CubeIDE

File Edit Navigate Search Project Run Window Help

Project Explorer HW22.ioc

HW22

- Includes
- Core
- Drivers
- HW22.ioc
- STM32F103C8TX_FLASH

HW22.ioc - Pinout & Configuration

Pinout & Configuration

A-Z

Categories

System...

DMA

GPIO

IWDG

NVIC

RCC

SYS

WWDG

Analog >

Timers >

Connect... >

Computi... >

Middlew... >

SYS Mode and Configuration

Mode

Debug No Debug

☐ System Wake-Up

Timebase Source SysTick

Configuration

Warning: This peripheral has no parameters to be configured.

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

Pinout view

System view

Pinout diagram of STM32F103C8Tx LQFP48 package. The diagram shows the chip with pins labeled PA0 through PA15, PB0 through PB15, VDD, VSS, VBAT, NRST, and various I/O pins like PC13, PC14, PC15, PD0-O, PD1-O, VSSA, VDDA, PA0, PA1, PA2, PA3, PA4, PA5, PA6, PA7, PA8, PA9, PA10, PA11, PA12, PA13, PA14, PA15. It also shows connections for FAN, button1, button2, button3, and I2C_SCL, I2C_SDA. The chip is labeled STM32F103C8Tx LQFP48.

Windows taskbar: 11:38:26

workspace_1.9.0 - Device Configuration Tool - STM32CubeIDE

File Edit Navigate Search Project Run Window Help

Project Explorer HW22.ioc

HW22

- Includes
- Core
- Drivers
- HW22.ioc
- STM32F103C8TX_FLASH

HW22.ioc - Pinout & Configuration

Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs Pinout

Pinout view System view

TIM3 Mode and Configuration

Mode

Slave Mode

Trigger Source

☒ Internal Clock

Channel1

Channel2

Channel3

Channel4

Combined Channels

☐ XOR activation

Configuration

Reset Configuration

☒ NVIC Settings ☒ DMA Settings

☒ Parameter Settings ☒ User Constants

Configure the below parameters :

Search (Ctrl+F)

Counter Settings

Prescaler (PSC - 16 bits v... 7999)

Counter Mode Up

Counter Period (AutoRelo... 499)

Internal Clock Division (CK.. No Division)

auto-reload preload Disable

Trigger Output (TRGO) Param...

Master/Slave Mode (MSM .. Disable (Trigger input effect not del...)

Trigger Event Selection Reset (UG bit from TIMx. EGR)

HW22.ioc - Clock Configuration

Pinout & Configuration

Clock Configuration

Project Manager

Tools

Resolve Clock Issues

