

to get Description of table

(7)

SYNTAX:

DESC {table-name}

Eg:

DESC employee;

o/p

<u>Field</u>	<u>Type</u>	<u>Null</u>	<u>key</u>	<u>Default</u>	<u>Extra</u>
FN	varchar(30)	YES		NULL	
LN	(40)	YES		NULL	
L	(20)	YES		NULL	
S	int	YES		NULL	

Inserting data into a table

SYNTAX: METHOD 1

INSERT INTO {table-name} values (" ", " ; " ")

Eg:

INSERT INTO employee values ("Monisha", "Periyasamy",
21, 100000, Coimbatore)

[The order of the values is in the same order as the columns in the table]

8

METHOD 2: (the correct values must be provided for the col specified, can't be null)

SYNTAX:

INSERT INTO {table-name} (col1, col2, ...) VALUES ("", ...)

Eg:

[The order of the values is in the same order as the columns specified now]

INSERT INTO employee (Salary, Location, FirstName, LastName) VALUES (27, Erode, "Neeraj", "Chopra");

Important of Semicolon;

→ Not all RDBMS software req; but some of the software like MySQL require semicolon to run multiple query at a time. Eg: Inserting multiple values in a table.

Dropping a table

Syn DROP TABLE {table-name}

Eg: DROP TABLE employee

CONSTRAINT

① NOT NULL

To make sure that the particular column value is not null,

```
CREATE TABLE EMPLOYEE (  
    FIRSTNAME varchar(30) NOT NULL,  
    LASTNAME varchar(30) NOT NULL,  
    AGE int NOT NULL,  
    Salary int NOT NULL,  
    Location int NOT NULL);
```

② PRIMARY KEY

METHOD 1

```
CREATE TABLE employee (  
    Emp-id bigint PRIMARY KEY  
);
```

There is no
Long datatype in
MySQL.

Not valid
datatype

METHOD 2

```
CREATE TABLE employee (  
    Emp-id int,  
    .....  
    PRIMARY KEY (Emp-id)  
);
```

[Primary key cannot be NOT NULL (by default)]

③ AUTOINCREMENT

⑩

→ There can be only one column with Autoincrement in the table

→ That column should be NOT NULL,

it is not necessary to be a primary key.

which is automatically NOT NULL by default

~~SQL~~

CREATE TABLE employee (

Emp-id int AUTO-INCREMENT,

FIRSTNAME Varchar NOTNULL,

);

~~Query~~

Desc employee

Field	Type	Null	key	Default	Extra
Emp-id	int	NO	PRI		autoincrement
FN	varchar(30)	NO			
LN	varchar(30)	NO			
Age	int	NO			
Location	varchar(40)	NO			
Salary	int	NO			

while inserting values into the table,
no need to specify col only

(11)

→ if ~~add~~ you inserting values for all col
in the order that matches the order in
table.

* → In this case Emp-id is auto-incremented
so we need not insert values for
that specific col.

So must specify the col-name

Query

```
INSERT INTO employee (FirstName, LastName, Age,  
Salary, Location) VALUES ("Moni", "Sha", 21, 80000,  
Bengaluru), ("Pri", "dharsh", 22, 60000, Chennai);
```

[to start auto increment from a specific
value cannot be defined in col def]

[can be done using alter command]

12

SELECT Command

✓ Select employee where is salary ≥ 50000

Query SELECT FirstName, LastName from employee
where Salary ≥ 50000 ;

ORDER BY (By default in ASCENDING ORDER)

✓ Select employee FN, LN, S where is Salary ≥ 50000 in descending order of Salary

Query SELECT FN, LN, S from employee
Where Salary ≥ 50000
ORDER BY Salary DESC;

LIMIT (to limit output)

only display top 2 records

Query SELECT FN, LN, S from employee
Where Salary ≥ 50000
ORDER BY Salary DESC
LIMIT 2;

(72)

ORDER OF EXECUTION

(72)

(13)

```
SELECT FirstName, LastName, Salary  
FROM Employee WHERE Salary >= 50000  
ORDER BY Salary DESC;
```

From → Where (Filter) → Select → Order by
↓
LIMIT

OFFSET (to omit a specified number of rows before the beginning of the result set)

✓ Select only top 4th & 5th employee FN, LN, S whose Salary >= 500 in descending order of salary

Query
SELECT FN, LN, S FROM employee
WHERE Salary >= 50000
ORDER BY Salary DESC

LIMIT 2 OFFSET 2;