NeonKey
neonkey.tech

Your Wi-Fi & Network Checkup

A free 30-minute self-check for your home or small business, from NeonKey

Who it's for: anyone who wants a safer, faster Wi-Fi network at home or at work. No technical background needed.
What you need: a phone or computer connected to your Wi-Fi, the sticker on your router, and about 30 minutes.
How it works: go step by step and tick one box for each: Already good, Fixed it, or Need help.

> **Before you change anything:** write down your current settings. Changing your Wi-Fi name or password will disconnect your devices, so have the new password ready to type in. If a step looks unfamiliar or you're unsure, skip it and mark "Need help".

0 Get ready

Find the sticker on your router and note its brand and model. Connect a phone or computer to your Wi-Fi. Open the router's settings page in a web browser using the address on the sticker or in the router's app (often something like **192.168.0.1** or **192.168.1.1**). Some routers can only be managed with the maker's phone app; that's fine, use the app.

Why it matters: You can't check settings you can't see, and the model tells you which updates apply to you.

☐ Already good ☐ Fixed it ☐ Need help

Notes: _____

1 Change the admin password

When you sign in to the router's settings, is the password still the factory default (like "admin") or the one printed on the sticker? If so, change it to a long, unique password and save it in a password manager.

Why it matters: Anyone who guesses the default password can change every setting on your network.

☐ Already good ☐ Fixed it ☐ Need help

Notes: _____

2 Update the router's software

The router's built-in software is called firmware. Look for a firmware or software update option in the settings or app (often under System, Administration or Advanced). Install any update, and turn on automatic updates if offered.

Why it matters: Updates fix security holes that attackers already know about.

☐ Already good ☐ Fixed it ☐ Need help

Notes: _____

3 Check your Wi-Fi name and password

Your Wi-Fi network name (SSID) shouldn't reveal your name, address or router brand. Your Wi-Fi password should be long; a short sentence works well. Remember: changing these disconnects your devices until you reconnect them.

Why it matters: A generic name gives strangers fewer clues, and a long password is much harder to guess.

☐ Already good ☐ Fixed it ☐ Need help

Notes: _____

4 Use the strongest security type

In the wireless security settings, choose Wi-Fi Protected Access 3 (WPA3). If older devices can't connect, choose the WPA2/WPA3 mixed mode. Turn off Wi-Fi Protected Setup (WPS), the push-button pairing feature.

Why it matters: WPA3 is the newest lock for Wi-Fi; push-button pairing is a known weak spot.

☐ Already good ☐ Fixed it ☐ Need help

Notes: _____

5 Set up a guest network

Turn on the guest network with its own password, and choose the option that stops guests from seeing your other devices. Put visitors, smart TVs and smart gadgets on it.

Why it matters: If a visitor's phone or a cheap gadget gets hacked, it can't reach your computers or files.

☐ Already good ☐ Fixed it ☐ Need help

Notes: _____

6 Turn off remote access

Find remote management or remote access (controlling the router from outside your home or office) and turn it off, unless you intentionally use the maker's app to manage it while away.

Why it matters: Fewer doors open to the internet means fewer ways in.

☐ Already good ☐ Fixed it ☐ Need help

Notes: _____

7 Check who's connected

Open the list of connected devices (often called Clients or Device List). Write each one below. If you don't recognize one, change your Wi-Fi password.

Why it matters: An unknown device could be a neighbor using your Wi-Fi, or something worse.

Device name	Recognized? Y / N	Action

☐ Already good ☐ Fixed it ☐ Need help

Notes: _____

8 Test your speed

Go to **speedtest.net** and run a test before you change anything and again when you finish. Write the results below.

Why it matters: It shows your changes didn't slow things down and gives you a baseline for later.

	Download (Mbps)	Upload (Mbps)	Ping (ms)
Before			
After			

☐ Already good ☐ Fixed it ☐ Need help

Notes: _____

For small businesses

Separate guest Wi-Fi for customers. Give customers their own guest network and password, never your main one.

☐ Already good ☐ Fixed it ☐ Need help

Keep business devices off guest Wi-Fi. Payment terminals and point-of-sale (POS) systems, plus office computers, stay on your main network only.

☐ Already good ☐ Fixed it ☐ Need help

Know who has the admin password. Store it in a password manager, limit who knows it, and change it when staff leave.

☐ Already good ☐ Fixed it ☐ Need help

Your score

Already good	Fixed it	Need help

Stuck on any "Need help" items? NeonKey can do it for you remotely.
See our services at **neonkey.tech/services/** or get in touch at **neonkey.tech/contact/**.