





Server Manager

Server Manager • Dashboard

Manage Tools View Help

Dashboard

Local Server

All Servers

File and Storage Services

IIS

WELCOME TO SERVER MANAGER

QUICK START

WHAT'S NEW

LEARN MORE

1 Configure this local server

2 Add roles and features

3 Add other servers to manage

4 Create a server group

5 Connect this server to cloud services

Hide

ROLES AND SERVER GROUPS

Roles: 2 | Server groups: 1 | Servers total: 1

File and Storage Services 1

Manageability

Events

Performance

BPA results

IIS 1

Manageability


Events


Services

Performance

BPA results

```
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#exit
ROUTER#
*Jul 22 16:40:55.779: %SYS-5-CONFIG_I: Configured from console by console
ROUTER#show ip interf
ROUTER#show ip interface b
Interface      IP-Address      OK? Method Status      Protocol
Ethernet0/0    172.16.0.1      YES manual  up          up
Ethernet0/1    unassigned      YES TFTP   up          up
Ethernet0/2    50.0.0.1        YES manual  up          up
Ethernet0/3    unassigned      YES TFTP   down        down
ROUTER#
```





PNETLab | TopologyTerminal

Not secure49.204.127.18/store/public/admin/labs/terminal?terminals=eyJ0YWJzIjpjbeyJuY...

Win \* ROUTER \* DNS \* Winserver \* Linux-1 \*

```
ROUTER(config)#exit
ROUTER#
*Jul 24 09:39:20.194: %SYS-5-CONFIG_1: Configured from console by console
ROUTER#show p ip ietr
% Ambiguous command: "show p ip ietr"
ROUTER#show p ip inter
% Ambiguous command: "show p ip inter"
ROUTER#show ip inetr
ROUTER#show ip inter
ROUTER#show ip interface b
Interface          IP-Address      OK? Method Status      Protocol
Ethernet0/0        unassigned      YES TFTP   up          up
Ethernet0/1        unassigned      YES TFTP   up          up
Ethernet0/2        unassigned      YES TFTP   up          up
Ethernet0/3        unassigned      YES TFTP   down        down
ROUTER#conf term
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#inetr
ROUTER(config)#inter
ROUTER(config)#interface ether
ROUTER(config)#interface ethernet 0/0
ROUTER(config-if)#ip add 172.16.0.1 255.255.0.0
ROUTER(config-if)#no shutdown
ROUTER(config-if)#no shutdown
ROUTER(config-if)#exit
ROUTER(config)#int e0/1
ROUTER(config-if)#ip add 5.0.0.1 255.0.0.0
ROUTER(config-if)#no shut
ROUTER(config-if)#no shutdown
ROUTER(config-if)#exit
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#int e0/2
ROUTER(config-if)#ip add
*Jul 24 09:42:44.867: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
ROUTER(config-if)#ip add 50.0.0.1 255.0.0.0
ROUTER(config-if)#no shut
ROUTER(config-if)#no shutdown
ROUTER(config-if)#exit
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
```

PNETLab | Topology

Terminal

Not secure 49.204.127.18/store/public/admin/labs/terminal?terminals=eyJ0YWJzIjpibeyJuY...

Win x ROUTER x DNS x Winserver x Linux-1 x

DNS Manager


File Action View Help

DNS

- SERVER2016
  - Forward Lookup Zones
    - com
      - hotstar
      - netflix
    - Reverse Lookup Zones
    - Trust Points
    - Conditional Forwarders

| Name | Type     | Data        | Timestamp |
|------|----------|-------------|-----------|
| www  | Host (A) | 172.16.0.20 |           |

10:24 AM 7/24/2026





```
ENABLE=yes
NAME=Ethernet
IPADDRESS=172.16.0.10
CIDRLEN=16
NETWORK=172.16.0.0
NETMASK=255.255.0.0
GATEWAY=172.16.0.1
BROADCAST=172.16.255.255
DHCP=no
```

100

```
- /etc/sysconfig/network-scripts/ifcfg-eth0 1/10 10%
```