VICIDIAL Wiki VICIDIAL Issue Tracker

astGUIclient Project Site

vicidial.org VICIDIAL astGUIclient discussion forum

 ☑ FAQ
 ☑ Search
 ☒ Memberlist
 ☒ Usergroups
 ☒ Register
 Profile up Log in to check your private messages Log in

ViciBox Redux v.3 install notes




eflo.net Home



vicidial.org Forum Index -> ViciBox Server Install and Demo

| View previous topic :: View next topic | |
|--|--|
| Author | Message |
| Kumba | ☐ Posted: Thu Sep 09, 2010 4:57 am Post subject: ViciBox Redux v.3 install notes |
| oined: 17 Oct 2007 | This version includes many improvements over the other versions, such as: |
| osts: 293 | |
| ocation: Florida | - Multi-Server Installation |
| | - 64-Bit DB-Only installer (includes web) |
| | - 3rd Gen Lead Loader (SVN-Only) |
| | - OpenSuSE v.11.3 Base Distro |
| | - Kernel 2.6.34 |
| | - Asterisk v.1.4.27.1 |
| | - Dahdi v.2.3.0 |
| | - Wanpipe v.3.5.14 |
| | - Wanpipe Voicetime v.3.0.9 |
| | - ViciDial v.2.2.1 and SVN v.2.4-275 Build 100817-1423 |
| | - Online or Offline Install |
| | - Archive set-up script |
| | Installation Documents: http://download.vicidial.com/iso/vicibox/server/ViciBox_Redux_v3-Install.pdf http://download.vicidial.com/iso/vicibox/server/ViciBox_Redux_v3-Cluster.pdf |
| | http://www.novell.com/documentation/opensuse113/ |
| | neepi// www.novemeeni/ accamentation/ openicación/ |
| | Here are some noteworthy tidbits for installing: |
| | - Type 'os-install' to initiate the phase-1 OS install (required first everywhere) |
| | - Type 'vicibox-install' as always to initiate vicibox install |
| | - Type 'vicibox-db' to install the 64-bit DB Only install |
| | - Type 'archive-setup' to configure a server for archive |
| | Order of things for a multi-server install: |
| | 1) Install a DataBase Server (Non-negotiable) |
| | 2) Install a Web Server (may be included with DB) |
| | 3) If you want an archive server, install it here |
| | 4) Install the first Dialer (This MUST be done ONE AT A TIME!) |
| | 5) Install an additional Dialer (Again, this MUST be done ONE AT A TIME!) |
| | 6) Repeat step 4 individually until all additional dialer servers are installed |
| | |
| | The general idea is to do the Phase-1 install on all servers, put the servers into their final production network environment, then complete the Phase-2 install. This is because the final IP address of the servers are tied to each other through the database. |
| | The archive server can be installed at any time as it is not directly part of the ViciDial cluster bu an ancillary server. It is, however, more convenient to install it prior to the Dialers so that you can put in the information for it during the Dialer install. To set-up an archive server you simply need to install ViciBox Redux to phase 1 (OS Install), then just type 'archive-setup'. It will creat |

6/6/2011 1:41 AM



2 of 3 6/6/2011 1:41 AM



3 of 3 6/6/2011 1:41 AM