

The screenshot shows a Windows terminal window with the following content:

```

(.venv) PS C:\Users\jubay\ws> kubectl get pods
NAME                                READY   STATUS    RESTARTS   AGE
jensen-iot-api-d98c45cfb-brk5b      1/1     Running   0           23m
jensen-iot-api-d98c45cfb-cr7p7      1/1     Running   0           23m
jensen-iot-api-d98c45cfb-hws2p      1/1     Running   0           23m
jensenstore-api-57b9bb9464-hl6v8    1/1     Running   2 (29m ago) 9d
jensenstore-api-57b9bb9464-nkhk8    1/1     Running   2 (29m ago) 9d
jensenstore-api-57b9bb9464-tgldz    1/1     Running   2 (29m ago) 9d
(.venv) PS C:\Users\jubay\ws> kubectl delete pod jensenstore-api-57b9bb9464-tgldz
pod "jensenstore-api-57b9bb9464-tgldz" deleted from default namespace
(.venv) PS C:\Users\jubay\ws> kubectl get pods
NAME                                READY   STATUS    RESTARTS   AGE
jensen-iot-api-d98c45cfb-brk5b      1/1     Running   0           34m
jensen-iot-api-d98c45cfb-cr7p7      1/1     Running   0           34m
jensen-iot-api-d98c45cfb-hws2p      1/1     Running   0           34m
jensenstore-api-57b9bb9464-hl6v8    1/1     Running   2 (40m ago) 9d
jensenstore-api-57b9bb9464-nkhk8    1/1     Running   2 (40m ago) 9d
jensenstore-api-57b9bb9464-rxgl7    1/1     Running   0           10m
(.venv) PS C:\Users\jubay\ws> kubectl scale deployment jensen-iot-api --replicas=5
deployment.apps/jensen-iot-api scaled
(.venv) PS C:\Users\jubay\ws> kubectl get pods
NAME                                READY   STATUS    RESTARTS   AGE
jensen-iot-api-d98c45cfb-brk5b      1/1     Running   0           36m
jensen-iot-api-d98c45cfb-cr7p7      1/1     Running   0           36m
jensen-iot-api-d98c45cfb-hws2p      1/1     Running   0           36m
jensen-iot-api-d98c45cfb-nkmf1      1/1     Running   0           11s
jensen-iot-api-d98c45cfb-pz6br      1/1     Running   0           11s
jensenstore-api-57b9bb9464-hl6v8    1/1     Running   2 (42m ago) 9d
jensenstore-api-57b9bb9464-nkhk8    1/1     Running   2 (42m ago) 9d
jensenstore-api-57b9bb9464-rxgl7    1/1     Running   0           13m
(.venv) PS C:\Users\jubay\ws> kubectl get deployment
NAME          READY   UP-TO-DATE   AVAILABLE   AGE
jensen-iot-api 5/5      5            5           36m

```

The terminal window is titled "Terminal" and has tabs for "Output", "Debug Console", "Terminal", and "Ports". The "Terminal" tab is active. The background of the terminal is dark with light-colored text. The Windows taskbar is visible at the bottom of the terminal window, showing the Start button, a search bar, and several application icons. The HP logo is visible on the bottom bezel of the monitor.