

Overlay Chart

Indicators & Analysis / Chart Overlays | intermediate | 6 min read | DeepCharts Help Center | August 24, 2026

The Overlay Chart indicator draws the chart of a second financial instrument on top of your main chart, so you can monitor two markets in one window. It is the more configurable sibling of Overlay Symbol: instead of mirroring the main chart's timeframe, Overlay Chart lets you pick a completely independent chart type and parameters for the overlaid instrument.

What it is

Overlay Chart answers the question "what is that other market doing right now, on the resolution I choose?" without opening a second chart window. You select any symbol from your feed, give it its own chart type (time, range, volume, Renko and more), and DeepCharts renders it either in a separate panel or directly on top of your main price series.

Because the overlaid series can use a different scale than your main instrument, the indicator includes a secondary price axis option so both series stay readable.

When to use it

- You trade one instrument but take cues from a correlated one — for example watching an index future while trading a related market.
- You want a higher or lower resolution view of another symbol than your main chart uses (Overlay Symbol cannot do this — it always syncs to the main chart's timeframe).
- You are studying lead/lag or divergence behavior between two markets inside a single window.
- You want delta-colored candles on the overlaid series to compare order flow across instruments.

Quick start

1. Open the indicator menu on your chart and add **Overlay Chart**.
2. Open the indicator's settings.
3. Click **Select Symbol** and choose the instrument you want to overlay.
4. Set **Parameter Type** to the chart type you want for the overlay (for example **Minutes**) and enter its value in **Param 1** (for example 15 for a 15-minute series).
5. To draw the overlay on top of your main price series, select **Chart Area 1** at the top of the indicator window. Leaving it in its own area keeps the two series in separate panels.
6. If the two instruments trade at different price levels, enable **Use Secondary Axis** so the overlay gets its own scale.
7. Apply the settings.

[SCREENSHOT PLACEHOLDER] Main chart of one futures instrument with Overlay Chart active showing a second instrument's candlesticks rendered in Chart Area 1 on a secondary axis, both series clearly distinguishable by color
dc-en-over lay-chart-01.png

How to read it


Read the overlay as context, not as a signal by itself. The most common uses:

- **Correlation and divergence** — when two normally correlated markets stop moving together, the one lagging often resolves toward the leader. The overlay makes these moments visible bar by bar.
- **Relative strength** — compare the shape of the two series across the same session: which one made a new high first, which one held its low.

- **Scale awareness** — with **Use Secondary Axis** enabled, the two series are drawn on independent scales. Compare shapes and timing, not vertical distance; a visual crossover between the two lines has no meaning across different axes.

If you enable **Delta-based Color**, the overlaid candles are colored by their delta (buying vs. selling aggression) instead of open/close direction, letting you compare order flow across the two markets. See Orderflow 101: Bid, Ask, Aggressor and Delta for how delta is computed.

Settings reference

[SCREENSHOT PLACEHOLDER] Overlay Chart settings dialog open, showing the General parameters section with Select Symbol, Parameter Type dropdown expanded listing Minutes, Days, Weekly, Monthly, Vol Bars, Range, Volume, Trade, Renko, Seconds, Point Figure and Delta  dc-en-over lay-chart-02.png

General

Setting	What it does
Select Symbol	Click to choose the symbol to overlay on the main chart.
Parameter Type	The chart type for the overlaid series: Minutes, Days, Weekly, Monthly, Vol Bars, Range, Volume, Trade, Renko, Seconds, Point Figure or Delta .
Param 1	The reference parameter for time-based charts and for Range, Volume, Trade, Renko and Delta types; also the first parameter for Vol Bars and Point Figure charts.
Param 2	The second parameter, used only by the Vol Bars and Point Figure chart types.

Volume/Delta

Setting	What it does
Delta-based Color	Colors the overlay candles by their delta instead of open/close direction.
Open/Close Based Border	Colors the candlestick border by bullish/bearish (open vs. close) status, useful alongside delta-based body coloring.
Delta Input	Which database the delta calculation reads from: Volume or Trades . See Different Types of Input Data for Indicators.
Color Mode	Fade grades the color intensity by delta magnitude; Fixed uses a single solid color per direction.
Std. Dev. for Coloring	The standard deviation value that scales the fade intensity when Color Mode is set to Fade.

Subgraph

Setting	What it does
Border color	Border color of the overlay candles.
Fill color	Body fill color of the overlay candles.
Chart Style	How the overlaid series is drawn: Line, Candlestick, OHLC, Hidden or Candlebody .
Border width	Thickness of the candle borders.

Placement

Setting	What it does
Chart Area	Select Chart Area 1 at the top of the indicator window to draw the overlay in the main chart area; otherwise it renders in its own panel.
Use Secondary Axis	Gives the overlaid series its own price axis. Enable this whenever the two instruments trade on different price scales.

Tips and common mistakes

- **Forgetting the secondary axis** is the most common issue: with two instruments on very different price levels sharing one axis, one series flattens into an unreadable line. Enable **Use Secondary Axis**.
- If you only want the same timeframe as your main chart, use **Overlay Symbol** instead — it auto-syncs and needs less configuration.
- Mixing very different chart types (for example Renko overlay on a time-based main chart) is powerful but can mislead on timing, since Renko bars do not close on a clock. Interpret bar-to-bar alignment loosely.
- Delta-based coloring depends on bid/ask trade data from your feed; if delta looks empty or flat, check your feed's data type in **Different Types of Input Data for Indicators**.
- Use the **Line** or **Candlebody** chart styles when the overlay clutters the main series — a thinner representation keeps the main instrument readable.

Related articles

- [Overlay Symbol](#)
- [Overlay Timeframe Candlestick](#)
- [Correlation Viewer](#)
- [Different Types of Input Data for Indicators](#)
- [How to Change the Layout of Indicators](#)
- [Orderflow 101: Bid, Ask, Aggressor and Delta](#)