

# Trading from the Chart

Trading | intermediate | 5 min read | DeepDOM Help Center | August 24, 2026

This guide explains how to enable trading directly from a DeepDom chart, use the trading panel and Chart DOM, manage orders, and customize trading-related columns and markers.

## Enable Trading and Show the Trading Panel

[ SCREENSHOT PLACEHOLDER ] Trading from the Chart — Enable Trading and Show the Trading Panel (DeepDOM)  
dd-en-trading-from-the-chart-01.png

### *Enable trading on a chart*

To allow order entry from a chart:

Click the dollar icon in the upper-right corner of the chart, or

Open the chart Settings menu and enable Trading enabled .

### *Show the trading panel*

To display the trading panel below the chart:

Enable the Trading panel checkbox in the lower-right corner of the chart, or

Use the chart Settings menu and enable Show trading panel .

## Trading Panel and Cross Trading Mini/Micro

[ SCREENSHOT PLACEHOLDER ] Trading from the Chart — Trading Panel and Cross Trading Mini/Micro (DeepDOM)  
dd-en-trading-from-the-chart-02.png

At the top of the trading panel you can select the instrument used for order execution. DeepDom allows cross trading , for example viewing data from a Mini futures contract while executing orders on a Micro contract, without opening additional charts. For accurate volumetric analysis, always base your decisions on the main futures contract.

The panel also shows:

Open quantity – number of contracts or shares currently in the market.

Open P/L – unrealized profit or loss on the open position.

Daily P/L – profit or loss realized on the instrument for the current trading day.

## Trading Buttons and Basic Actions

[ SCREENSHOT PLACEHOLDER ] Trading from the Chart — Trading Buttons and Basic Actions (DeepDOM)  
dd-en-trading-from-the-chart-03.png

The trading panel includes quick-access buttons for different order types:

MKT – send buy or sell market orders.

BID / ASK – place limit orders at the current best Bid or best Ask.

LMT – place manual limit orders (buy limit below market price or sell limit above market).

STP – place stop orders that become market orders when triggered (buy stop above market, sell stop below market).

STP LMT – place stop-limit orders, which send limit orders instead of market orders when triggered, helping to control slippage at the risk of missing execution.

Cancel – cancel all working (pending) orders.

Close – close the current open position and cancel all remaining working orders.

Use the Qty , Broker , and Account fields to choose the trade size, broker, and account for each operation.

If the Tick diff. option is enabled, Bid and Ask buttons will place limit orders a specified number of ticks away from the market price instead of exactly at the best Bid/Ask.

## OCO Strategy and Historical Fills

### OCO Strategy

The OCO (Order■Cancels■Order) feature lets you attach two exit orders to a primary position: a profit■taking limit order and a protective stop. When one of these exit orders is executed, the other is automatically cancelled.

[ SCREENSHOT PLACEHOLDER ] Trading from the Chart — OCO Strategy (DeepDOM)  
dd-en-trading-from-the-chart-04.png

### Show historical executions

To display historical fills on the chart, open the chart settings and enable Show historical executions . Trade markers will then appear at the corresponding prices and times

[ SCREENSHOT PLACEHOLDER ] Trading from the Chart — Show historical executions (DeepDOM)  
dd-en-trading-from-the-chart-05.png

## Chart DOM Overview

[ SCREENSHOT PLACEHOLDER ] Trading from the Chart — Chart DOM Overview (DeepDOM)  
dd-en-trading-from-the-chart-06.png

The Chart DOM provides a vertical order book ladder next to your chart.

Enable it by selecting the DOM checkbox at the bottom■right of the chart, or

Open chart settings and enable Enable chart DOM .

By default, the Chart DOM shows these columns from left to right:

B.PS – Bid Pull Stack; quantities added or removed at each Bid level.

B – order■management column for buy orders (move or cancel).

Bid – buy■limit orders at each price level.

Ask – sell■limit orders at each price level.

S – order■management column for sell orders.

A.PS – Ask Pull Stack; quantities added or removed at each Ask level.

## Order Entry and Management on the DOM

### Market and limit/stop orders

Buy Market – right■click anywhere in the Bid column.

Sell Market – right■click anywhere in the Ask column.

Buy Limit – left■click in the Bid column at any price below the current market price.

Buy Stop – left■click in the Bid column at any price above the current market price.

Sell Limit – left■click in the Ask column at any price above the current market price.

Sell Stop – left■click in the Ask column at any price below the current market price.

### Modify and cancel orders

For existing limit or conditional orders:

Use the order management columns ( B and S ) and drag with the left mouse button to move an order to a new price level.

Right-click to cancel an order.

Double-click with the left mouse button to edit the order quantity.

## Chart DOM Settings and Columns

[ SCREENSHOT PLACEHOLDER ] Trading from the Chart — Chart DOM Settings and Columns (DeepDOM)  
dd-en-trading-from-the-chart-07.png

Click the Settings icon on the Chart DOM to open DOM settings. Here you can adjust Font size, Text format and the appearance of various columns, including:

[ SCREENSHOT PLACEHOLDER ] Trading from the Chart — Chart DOM Settings and Columns (DeepDOM)  
dd-en-trading-from-the-chart-08.png

Bid/Ask Columns – change background and text colors for Bid and Ask.

Pull Stack Columns – enable Bid/Ask Pull Stack, choose filters (average or none), and customize colors.

Filled filter – apply a filter to executed quantities so only significant trades are shown.

Bid/Ask Filled – show executed volumes in B.T (Bid Trades) and A.T (Ask Trades) columns, effectively forming a footprint view. Auto-reset can clear these based on price swings, or you can reset manually.

Last Filled – enable the last trade column.

Order View – show/hide order management columns and adjust their colors.

Price Scale – enable the price ladder column and customize its appearance.

P/L Column – display tick-by-tick unrealized profit and loss when you have an open position.

Markers – enable markers for last traded price, open, high, and low.

Column Order – open the column order settings to rearrange the DOM columns as needed.

## Still Having Trouble?

Our support team is available 24/7 and ready to help you with any issue you encounter. When you reach out, please include:

A screenshot of the issue.

A brief description of what you were trying to do.

Support Ticket (fastest response): visit [www.deepcharts.com](http://www.deepcharts.com) and create a support ticket directly on our website.

Email Support: you can also reach us at [support@deepcharts.com](mailto:support@deepcharts.com). Please note that email responses may take a little longer than a support ticket.