
Hosting Static Website in S3

Storage based lab

After completing this lab we will be able to

- 1. Create a bucket in Amazon S3
- 2. Upload content to your bucket
- 3. Enable access to the bucket objects
- 4. Update the website




Task 1:



Buckets

1: Choose for the S3 service in console



2: Choose **Buckets** option

3: Click on Create Bucket

Task 2: Fill every data needed to create bucket in create bucket section

- 1. Enter bucket name (name must be unique globally).
- 2. Select region.
- 3. Object ownership: ACL enabled and bucket owner preferred.
- 4. Public Access setting for bucket.
- 5. Bucket versioning.
- 6. Tags (optional).
- 7. Default encryption.
- 8. Finally, click on **create bucket**.

Create bucket Info

Buckets are containers for data stored in S3. Learn more

General configuration Bucket name Static-Website-Bucket-Mukesh Bucket name must be globally unique and must not contain spaces or uppercase letters. See rules for bucket naming AWS Region Asia Pacific (Mumbai) ap-south-1 ▼ Copy settings from existing bucket - optional Only the bucket settings in the following configuration are copied. Choose bucket

Object Ownership Info

Control ownership of objects written to this bucket from other AWS accounts and the use of access control lists (ACLs). Object ownership determines who can specify access to objects.

ACLs disabled (recommended)

All objects in this bucket are owned by this account. Access to this bucket and its objects is specified using only policies.

ACLs enabled

Objects in this bucket can be owned by other AWS accounts. Access to this bucket and its objects can be specified using ACLs.

rair onler omissinh Into

Object Ownership

Control ownership of objects written to this bucket from other AWS accounts and the use of access control lists (ACLs). Object ownership determines who can specify access to objects.

ACLs disabled (recommended)

All objects in this bucket are owned by this account. Access to this bucket and its objects is specified using only policies.

ACLs enabled

Objects in this bucket can be owned by other AWS accounts. Access to this bucket and its objects can be specified using ACLs.

Δ

Enabling ACLs turns off the bucket owner enforced setting for Object Ownership

Once the bucket owner enforced setting is turned off, access control lists (ACLs) and their associated permissions are restored. Access to objects that you do not own will be based on ACLs and not the bucket policy.

✓ I acknowledge that ACLs will be restored.

Object Ownership

Bucket owner preferred

If new objects written to this bucket specify the bucket-owner-full-control canned ACL, they are owned by the bucket owner. Otherwise, they are owned by the object writer.

- Object writer
 The object writer remains the object owner.
 - If you want to enforce object ownership for new objects only, your bucket policy must specify that the bucket-owner-full-control canned ACL is required for object uploads. Learn more

Block Public Access settings for this bucket

objects within becoming public.

Public access is granted to buckets and objects through access control lists (ACLs), bucket policies, access point policies, or all. In order to ensure that public access to this bucket and its objects is blocked, turn on Block all public access. These settings apply only to this bucket and its access points. AWS recommends that you turn on Block all public access, but before applying any of these settings, ensure that your applications will work correctly without public access. If you require some level of public access to this bucket or objects within, you can customize the individual settings below to suit your specific storage use cases. Learn more [7]

В	lock all public access
Tu	urning this setting on is the same as turning on all four settings below. Each of the following settings are independent of one another
- [Block public access to buckets and objects granted through <i>new</i> access control lists (ACLs) S3 will block public access permissions applied to newly added buckets or objects, and prevent the creation of new public access ACLs for existing buckets and objects. This setting doesn't change any existing permissions that allow public access to S3 resource using ACLs.
- [Block public access to buckets and objects granted through <i>any</i> access control lists (ACLs) S3 will ignore all ACLs that grant public access to buckets and objects.
- [Block public access to buckets and objects granted through <i>new</i> public bucket or access point policies S3 will block new bucket and access point policies that grant public access to buckets and objects. This setting doesn't change any existing policies that allow public access to S3 resources.
- [Block public and cross-account access to buckets and objects through <i>any</i> public bucket or access point policies
	S3 will ignore public and cross-account access for buckets or access points with policies that grant public access to buckets and objects.
_	Turning off block all public access might result in this bucket and the objects within becoming public AWS recommends that you turn on block all public access, unless public access is required for specific and
	verified use cases such as static website hosting.
	✓ I acknowledge that the current settings might result in this bucket and the

Bucket Versioning Versioning is a means of keeping multiple variants of an object in the same bucket. You can use versioning to preserve, retrieve, and restore every version of every object stored in your Amazon S3 bucket. With versioning, you can easily recover from both unintended user actions and application failures. Learn more **Bucket Versioning** Disable Enable Tags (2) - optional You can use bucket tags to track storage costs and organize buckets. Learn more [2] Value - optional Key Owner Mukesh Remove Environment Intern-Test Remove Add tag

Default encryption Info

Server-side encryption is automatically applied to new objects stored in this bucket.

Encryption key type Info

Environment	Intern Test	Persons
Environment	Intern-Test	Remove
Add tag		
Default encryption Info		
Server-side encryption is automatical	ally applied to new objects stored in this bucket.	
Encryption key type Info		
Amazon S3 managed keys	(SSE-S3)	
AWS Key Management Service	vice key (SSE-KMS)	
Bucket Key When KMS encryption is used to end Learn more	rypt new objects in this bucket, the bucket key redu	uces encryption costs by lowering calls to AWS KMS.
○ Disable		
Enable		
► Advanced settings		
The state of the s		
0.4		
 After creating the bucket y 	ou can upload files and folders to the bucke	et and contigure additional bucket settings

Static-website-bucket-mukesh

Objects Properties Permissions Metrics Management Access Points

Bucket overview

AWS Region
Asia Pacific (Mumbai) ap-south-1

Amazon Resource Name (ARN)

The arn:aws:s3:::static-website-bucket-mukesh

Creation date
March 22, 2023, 13:49:20 (UTC+05:45)

Static website hosting	
Disable	
• Enable	
Hosting type	
Host a static website	
Use the bucket endpoint as the web address. Learn m	nore 🔀
Redirect requests for an object	
readable. To do so, you can edit the S3 Blo	ne website endpoint, you must make all your content publicly ock Public Access settings for the bucket. For more information, see
Redirect requests to another bucket or domain. Learn 3 For your customers to access content at the	ne website endpoint, you must make all your content publicly
For your customers to access content at the readable. To do so, you can edit the S3 Blo	ne website endpoint, you must make all your content publicly
For your customers to access content at the readable. To do so, you can edit the S3 Blo Using Amazon S3 Block Public Access □	ne website endpoint, you must make all your content publicly
For your customers to access content at the readable. To do so, you can edit the S3 Block Public Access Using Amazon S3 Block Public Access □ ndex document	ne website endpoint, you must make all your content publicly
For your customers to access content at the readable. To do so, you can edit the S3 Blo Using Amazon S3 Block Public Access □ Index document Specify the home or default page of the website. Index.html Error document - optional	ne website endpoint, you must make all your content publicly
For your customers to access content at the readable. To do so, you can edit the S3 Bloc Using Amazon S3 Block Public Access □ Index document Specify the home or default page of the website. Index.html	ne website endpoint, you must make all your content publicly

Task 3: Working in bucket

- 1. Select properties tab.
- 2. Scroll down to **static website hosting.**
- 3. Then perform following task:

Configure the following settings:

- Static web hosting: Enable
- Hosting type: Host a static website
- Index document: index.html
 - Note: You must enter this value, even though it is already displayed.
- Error document: error.html

Choose Save changes

Task 4: Uploading content to bucket

- 1. Select objects tab.
- 2. Click in the <u>upload</u> option.
- 3. Browse the website files from local device and upload them.

Note:

We can also update the data that is uploaded in the bucket in the local device and re-upload the data in cloud after updating it. For eg: we can update "index.html" file and the re-upload it.

Task 5: Enabling access to the objects

Objects stored in S3 are private by default which ensures the security of the data. In this lab we will make the objects publicly accessible.

There are two ways to make S3 objects public:

- 1. Make whole bucket public or some directory in bucket public using a **bucket policy**.
- 2. Make individual objects public using ACL.

Steps:

- Select the uploaded objects.
- Choose make public via ACL from actions tab.
- 3. Choose make public.

Task 6: We can now access the website using link from static website hosting option from properties tab



MUKESH AWASTHI

Demo of the static website