Prof. Thomas Brox WS 2021/2022

Figure 1: Examples of distribution shift

## 1. Installation

We assume that you have installed python 3.8 using miniconda as described in the setup instructions in the setup.pdf on the website of the Computer Vision lecture. You should know how to navigate and run commands in the command prompt.

In your miniconda environment, install the latest versions of PyTorch and TorchVision as described on PyTorch's website. To use a GPU install PyTorch with the compute platform cuda, usually selecting CUDA 10.2 will work.

## 2. Accessing the data

The data file for this exercise data.tar can be found on server of the technical faculty in /project/cv-ws2122/shared-data1/data.

## 3. Batch Normalization and Distribution shift

CNNs are known to perform well when the test and training data are sampled from the same distribution (i.e are i.i.d). However, in many real world scenarios this assumption does not hold. Images might differ from the training data if lighting conditions change or if dirt particles accumulate on the camera. In medical imaging, MRI scans will differ from the training data if different acquisition systems are being used. While human vision is robust to such distribution shifts, modern machine vision models are not.

In computer vision, Batch Normalization (BN) is a popular technique to improve convergence of CNNs. BN estimates the statistics of activations for the training dataset and uses them to normalize intermediate activations in the network. By design, activation statistics obtained during training time do not reflect the statistics of the test distribution (Eg: when testing in out-of-distribution settings like corrupted images). Adapting BN statistics at test time is a popular technique for domain adaptation to new distributions, which is the goal of this exercise. Some examples of distribution shifts are shown in Figure 1.

In this exercise we will be using a pre-trained model and implement a method for updating BN statistics. The code for running evaluations is ex04/run\_resnet.py where you have to implement the function update\_bn\_params. This method takes the model, the data loader and command line arguments. The number of iterations can be set using the arugment num\_bn\_updates. The script already has options to load different datasets with distribution shifts (common corruptions). The available corruptions are: 'defocus\_blur', 'glass\_blur', 'motion\_blur', 'zoom\_blur', 'snow', 'frost', 'fog', 'brightness'. You can also control the corruption severity using the severity flag (range is from 1 to 5).

Todo: Run run\_resnet.py --clean\_eval to test the network on clean images and report the performance.

**Todo:** Run run\_resnet.py --evaluate To check the impact of all corruption types at different levels of severity.

This can take quite a while to complete so you can also run e.g run\_resnet.py --corruption "frost" --severity 2 to test individual corruptions at a chosen severity.

**Todo:** Fill in the Todo block around the update\_bn\_params function in order to briefly train on the validation set, so the batch norm can be updated before validation.

Todo: Now, run run\_resnet.py --apply\_bn and compare your results to the unadapted version.

Todo: Set the number of batch norm updates as a the hyper parameter --num\_bn\_updates and play around

with it to see how it affects performance.

**Todo:** Keep the number of updates fixed to 50 and consider the following batch sizes: 1, 4, 16, 64. Explain your observations.

This assignment will be discussed on 2.12. 13:00-14:00 CET.