

MS Word MCP server

Integrates with Microsoft Word documents to enable reading, writing, and editing of text, tables, and images for automated document processing and content generation.

← Back to servers

Setup instructions

[Claude Code](#)

[Cursor](#)

[Claude Desktop](#)

Provider

famano

Release date

Jan 21, 2025

Language



Adding a new feature to a project with Factory CLI

Python

Stats

27 stars

View Markdown

View on GitHub

The MCP Server Office enables you to read, write, and edit Microsoft Word (docx) files through a Model Context Protocol server interface, making document manipulation programmatically accessible.

Installation

Install the MCP server using pip:

```
pip install mcp-server-office
```

If you prefer using uv:

```
uvx mcp-server-office
```

Starting the Server



Adding a new feature to a project with Factory CLI

Start the MCP server by running:

```
mcp-server-office
```

Available Tools

The server provides four main tools for working with Word documents:

Read DOCX Files

The `read_docx` tool extracts the complete contents of a docx file, including tables and images.

Input parameters:

- `path` (string) - Absolute path to the target file

Note: Images appear as `[Image]` placeholders, and track changes in the output.

Write DOCX Files

The `write_docx` tool creates new docx files with content you supply.

Input parameters:



Adding a new feature to a project with Factory CLI

- `path` (string) - Absolute path to the target file
- `content` (string) - Content to write to the file

Formatting guidelines:

- Use double line breaks to create new paragraphs
- Use `[Table]` tag with `|` separators to create tables

Edit DOCX Paragraphs

The `edit_docx_paragraph` tool makes text replacements in specific paragraphs of a docx file.

Input parameters:

- `path` (string) - Absolute path to the file to edit
- `edits` (array) - List of dictionaries containing:
 - `paragraph_index` (number) - 0-based index of the paragraph
 - `search` (string) - Text to find within the specified paragraph
 - `replace` (string) - Text to replace with

Note: Each search string must match exactly once within the specified paragraph.

Insert Content into DOCX Files



Adding a new feature to a project with Factory CLI

The `edit_docx_insert` tool inserts new paragraphs into a docx file.

Input parameters:

- `path` (string) - Absolute path to the file to edit
- `inserts` (array) - List of dictionaries containing:
 - `text` (string) - Text to insert as a new paragraph
 - `paragraph_index` (number, optional) - 0-based index of the paragraph before which to insert. If not specified, the text will be inserted at the end.

System Requirements

- Python 3.12 or newer
- Required dependencies (installed automatically):
 - `mcp[cli] ≥ 1.2.0`
 - `python-docx ≥ 1.1.2`

How to install this MCP server

For Claude Code

To add this MCP server to Claude Code, run this command in your



Adding a new feature to a project with Factory CLI

```
claude mcp add-json "mcp-server-office" '{"command":"mcp-server-office","a1
```

See the [official Claude Code MCP documentation](#) for more details.

For Cursor

There are two ways to add an MCP server to Cursor. The most common way is to add the server globally in the `~/.cursor/mcp.json` file so that it is available in all of your projects.

If you only need the server in a single project, you can add it to the project instead by creating or adding it to the `.cursor/mcp.json` file.

Adding an MCP server to Cursor globally

To add a global MCP server go to Cursor Settings > Tools & Integrations and click "New MCP Server".

When you click that button the `~/.cursor/mcp.json` file will be created and you can add your server like this:

```
{
  "mcpServers": {
    "mcp-server-office": {
      "command": "mcp-server-office",
      "args": []
    }
  }
}
```



Adding a new feature to a project with Factory CLI

```

    }
  }
}

```

Adding an MCP server to a project

To add an MCP server to a project you can create a new `.cursor/mcp.json` file or add it to the existing one. This will look exactly the same as the global MCP server example above.

How to use the MCP server

Once the server is installed, you might need to head back to Settings > MCP and click the refresh button.

The Cursor agent will then be able to see the available tools the added MCP server has available and will call them when it needs to.

You can also explicitly ask the agent to use the tool by mentioning the name of the tool and describing what the function does.

For Claude Desktop

To add this MCP server to Claude Desktop:

1. Find your configuration file:



Adding a new feature to a project with Factory CLI

- **macOS:** ~/Library/Application Support/Claude/claude_desktop_config.json
- **Windows:** %APPDATA%\Claude\claude_desktop_config.json
- **Linux:** ~/.config/Claude/claude_desktop_config.json

2. Add this to your configuration file:

```
{
  "mcpServers": {
    "mcp-server-office": {
      "command": "mcp-server-office",
      "args": []
    }
  }
}
```

3. Restart Claude Desktop for the changes to take effect

 Privacy / Terms / Advertise



Adding a new feature to a project with Factory CLI