

Installing Moodle

Visit your Moodle domain name such as <https://moodle.howtoforge.local/> and you'll see the installation wizard.

Select your default language and click **Next**.

Installation

Language

Choose a language

Please choose a language for the installation. This language will also be used as the default language for the site, though it may be changed later.

Language

English (en) ▾

Next »



Input your data directory for Moodle `'/var/www/moodledata'`.

Confirm paths

Web address

The full address where Moodle will be accessed i.e. the address that users will enter into the address bar of their browser to access Moodle.

It is not possible to access Moodle using multiple addresses. If your site is accessible via multiple addresses then choose the easiest one and set up a permanent redirect for each of the other addresses.

If your site is accessible both from the Internet, and from an internal network (sometimes called an Intranet), then use the public address here.

If the current address is not correct, please change the URL in your browser's address bar and restart the installation.

Moodle directory

The full path to the directory containing the Moodle code.

Data directory

A directory where Moodle will store all file content uploaded by users.

This directory should be both readable and writeable by the web server user (usually 'www-data', 'nobody', or 'apache').

It must not be directly accessible over the web.

If the directory does not currently exist, the installation process will attempt to create it.

Web address

http://moodle.howtoforge.local

Moodle directory

/var/www/moodle

Data directory

/var/www/moodledata

« Previous

Next »

Select the **MariaDB** as the database driver.

Installation

Database

Choose database driver

Moodle supports several types of database servers. Please contact server administrator if you do not know which type to use.

Type

[« Previous](#) [Next »](#)



Enter details of your MariaDB database and user.

Database settings

MariaDB (native/mariadb)

The database is where most of the Moodle settings and data are stored and must be configured here.

The database name, username, and password are required fields; table prefix is optional.

The database name may contain only alphanumeric characters, dollar (\$) and underscore (_).

If the database currently does not exist, and the user you specify has permission, Moodle will attempt to create a new database with the correct permissions and settings.

This driver is not compatible with legacy MyISAM engine.

Database host

Database name

Database user

Database password

Tables prefix

Database port

Unix socket

[« Previous](#) [Next »](#)

Click **Continue** to confirm the copyright notice.

Installation

Moodle - Modular Object-Oriented Dynamic Learning Environment

Copyright notice

Copyright (C) 1999 onwards Martin Dougiamas (<https://moodle.com>)

This program is free software: you can redistribute it and/or modify it under the terms of the GNU General Public License as published by the Free Software Foundation, either version 3 of the License, or (at your option) any later version.

This program is distributed in the hope that it will be useful, but WITHOUT ANY WARRANTY; without even the implied warranty of MERCHANTABILITY or FITNESS FOR A PARTICULAR PURPOSE.

See the Moodle License information page for full details: <https://moodledev.io/general/license>

Confirm

Have you read these conditions and understood them?

Cancel

Continue

On the server checks section, make sure your environment is ready.

Installation - Moodle 4.4.1+ (Build: 20240802)

Moodle 4.4.1+ (Build: 20240802)

For information about this version of Moodle, please see the online [Release Notes](#)

Server checks

Name	Information	Report	Plugin	Status
unicode		must be installed and enabled		
database	mariadb (10.11.8-MariaDB-0ubuntu0.24.04.1)	version 10.6.7 is required and you are running 10.11.8		
php		version 8.1.0 is required and you are running 8.3.6		
preunicode		should be installed and enabled for best results		
php_extension	iconv	must be installed and enabled		
php_extension	mbstring	must be installed and enabled		
php_extension	curl	must be installed and enabled		
php_extension	openssl	must be installed and enabled		
php_extension	tokenizer	should be installed and enabled for best results		
php_extension	soap	should be installed and enabled for best results		
php_extension	ctype	must be installed and enabled		
php_extension	zip	must be installed and enabled		
php_extension	zlib	must be installed and enabled		
php_extension	gd	must be installed and enabled		
php_extension	simplexml	must be installed and enabled		

Now the Moodle installation will be processed.

factor_nosetup

Success (0.05 seconds)

factor_role

Success (0.11 seconds)

factor_sms

Success (0.09 seconds)

factor_token

Success (0.05 seconds)

factor_totp

Success (0.05 seconds)

factor_webauthn

Success (0.05 seconds)

Continue

After the installation is complete, enter the new admin user, email, and password for Moodle.

Installation

On this page you should configure your main administrator account which will have complete control over the site. Make sure you give it a secure username and password as well as a valid email address. You can create more admin accounts later on.

Expand all

General

Username

admin

Choose an authentication method

Manual accounts

New password

The password must have at least 8 characters, at least 1 digit(s), at least 1 lower case letter(s), at least 1 upper case letter(s), at least 1 special character(s) such as *, -, or #

Force password change

First name

Admin

Last name

User

Email address

admin@howtoforge.local

Email visibility

Visible to everyone

City/town

Now you'll see the Moodle dashboard like the following:

Welcome, Admin! 🖐️

Timeline

Next 7 days ▾

Sort by dates ▾

Search by activity type or name

No in-progress courses

Calendar

All courses ▾

New event

◀ July

August 2024

September ▶

Mon	Tue	Wed	Thu	Fri	Sat	Sun
			1	2	3	4
5	6	7	8	9	10	11