1. Create a user account with the following attribute

username: islam

Fullname/comment: Islam Askar

Password: islam

2.

Create a user account with the following attribute

Username: baduser

Full name/comment: Bad User

Password: baduser

```
To run a command as administrator (user "root"), use "sudo <command>".

See "man sudo_root" for details.

nader@nader-Latitude-E5530-vPro:~$ sudo useradd islam -c "Islam Askar"
[sudo] password for nader:
nader@nader-Latitude-E5530-vPro:~$ sudo passwd islam
New password:
Retype new password:
passwd: password updated successfully
nader@nader-Latitude-E5530-vPro:~$ sudo useradd baduser -c "bad user"
nader@nader-Latitude-E5530-vPro:~$ sudo passwd baduser
New password:
Retype new password:
passwd: password updated successfully
```

3. Create a supplementary (Secondary) group called Secondary with group ID of 30000

```
nader@nader-Latitude-E5530-vPro:~$ sudo groupadd secondary -g 30000
```

4. Create a supplementary group called badgroup

```
nader@nader-Latitude-E5530-vPro:~$ sudo groupadd badgroup
nader@nader-Latitude-E5530-vPro:~$ cat /etc/passwd
```

```
islam:x:1001:1001:Islam Askar:/home/islam:/bin/sh
baduser:x:1002:1002:bad user:/home/baduser:/bin/sh
nader@nader-Latitude-E5530-vPro:~$
```

```
secondary:x:30000:
badgroup:x:30001:
nader@nader-Latitude-E5530-vPro:~$
```

5. Add islam user to the pgroup secondary as a supplementary group

```
ader@nader-Latitude-E5530-vPro:~$ sudo usermod -G secondary islam
ader@nader-Latitude-E5530-vPro:~$ id islam
id=1001(islam) gid=1001(islam) groups=1001(islam),30000(secondary)
ader@nader-Latitude-E5530-vPro:~$
```

6. Modify the password of islam's account to password

```
nader@nader-Latitude-E5530-vPro:~$ id islam
uid=1001(islam) gid=1001(islam) groups=1001(islam),30000(secondary)
nader@nader-Latitude-E5530-vPro:~$ sudo passwd islam
New password:
Retype new password:
passwd: password updated successfully
nader@nader-Latitude-E5530-vPro:~$
```

Modify islam's account so the password expires after 30 days

```
nader@nader-Latitude-E5530-vPro:~$ sudo chage -M 30 islam
nader@nader-Latitude-E5530-vPro:~$ sudo chage -l islam
ast password change
                                                         مار 16, 2023 :
assword expires
                                                         ابر 15, 2023 :
assword inactive
                                                         : never
account expires
                                                         : never
linimum number of days between password change
                                                         : 0
laximum number of days between password change
                                                         : 30
lumber of days of warning before password expires
                                                         : 7
ader@nader-Latitude-E5530-vPro:~S
```

8. Lock bad user account so he can't log in

```
nader@nader-Latitude-E5530-vPro:~$ sudo passwd -l baduser
passwd: password expiry information changed.
nader@nader-Latitude-E5530-vPro:~$
```

9. Delete bad user account

```
nader@nader-Latitude-E5530-vPro:~$ sudo userdel baduser
nader@nader-Latitude-E5530-vPro:~$
```

10. Delete the supplementary group called badgroup.

```
iader@nader-Latitude-E5530-vPro:~$ sudo groupdel badgroup
iader@nader-Latitude-E5530-vPro:~$
```