

Percussion MIDI Maps

A Percussion MIDI Map is simply a list that matches each percussion instrument in a sound library with a particular MIDI note number (e.g. bass drum = 36, snare drum = 38, etc.). These maps are required to properly assign the same percussion notation to various playback devices, and are also used to accommodate the many different percussion sound banks that can be used for input with an external MIDI device.

To playback your percussion parts using the correct instrument sounds, ensure the appropriate Percussion MIDI Map is selected under the Percussion Map column of the [ScoreManager](#).

Note that you can choose **MIDI/Audio > Device Setup > MIDI Thru** to audition the percussion sounds SongWriter interprets if you want to use your MIDI keyboard for input and not for playback.

SmartMusic SoftSynth Percussion MIDI Maps

This listing contains all the General MIDI percussion sounds used in the various SmartMusic SoftSynth Percussion MIDI Maps. These percussion sounds are available when using SongWriter's SmartMusic SoftSynth (with SmartMusic SoftSynth chosen as the MIDI Out device in the [MIDI Setup](#) dialog box). You must also ensure the desired Percussion MIDI Map is selected for the percussion staff under the "Perc. MIDI Map" column of the [ScoreManager](#) (SmartMusic SoftSynth submenu). This setting in the ScoreManager is set automatically when you choose a percussion instrument from the Setup Wizard or add it with the ScoreManager.

Tip: To see the relationship between MIDI Note numbers and pitches on a piano keyboard see the [MIDI Note to Pitch Table](#).

General MIDI

MIDI Note Number	Note Type	MIDI Note Number	Note Type
27	Laser	60	High Bongo
28	Whip	61	Low Bongo
29	Scratch Push	62	Conga Dead Stroke
30	Scratch Pull	63	Conga
31	Stick Click	64	Tumba
32	Metronome Click	65	High Timbale
34	Metronome Bell	66	Low Timbale
35	Bass Drum	67	High Agogo
36	Kick Drum	68	Low Agogo
37	Snare Cross Stick	69	Cabasa
38	Snare Drum	70	Maracas
39	Hand Clap	71	Whistle Short
40	Electric Snare Drum	72	Whistle Long
41	Floor Tom 2	73	Guiro Short
42	Hi-Hat Closed	74	Guiro Long
43	Floor Tom 1	75	Claves
44	Hi-Hat Foot	76	High Woodblock
45	Low Tom	77	Low Woodblock
46	Hi-Hat Open	78	Cuica High
47	Low-Mid Tom	79	Cuica Low
48	High-Mid Tom	80	Triangle Mute
49	Crash Cymbal	81	Triangle Open
50	High Tom	82	Shaker
51	Ride Cymbal	83	Sleigh Bell
52	China Cymbal	84	Bell Tree
53	Ride Bell	85	Castanets
54	Tambourine	86	Surdu Dead Stroke
55	Splash cymbal	87	Surdu
56	Cowbell	91	Snare Drum Rod
57	Crash Cymbal 2	92	Ocean Drum
58	Vibraslap	93	Snare Drum Brush
59	Ride Cymbal 2		

Row-Loff Marching Percussion

MIDI Note Number	Note Type	MIDI Note Number	Note Type
36	Bass Drum 5	66	Low Tom Shot/Rim
37	Bass Drum Rim	67	Low Tom Short Roll
38	Bass Drum 4	69	Low-Mid Tom
39	Bass Drum Unison Hits	70	Low-Mid Tom Shot/Rim
40	Bass Drum 3	71	Low-Mid Tom Short Roll
41	Bass Drum 2	72	High-Mid Tom
42	Bass Drum Roll	73	High-Mid Tom Shot/Rim
43	Bass Drum	74	Hi-Mid Tom Short Roll
44	Crash Cymbals Crash	76	High Tom
45	Cymbal Section Crash	76	Floor Tom 1
46	Cymbal Section Hi Hat Choke	76	Floor Tom 2
47	Crash Cymbals Choke Fat	77	High Tom Shot/Rim
48	Snare Section Hits LH	78	High Tom Short Roll
49	Snare Rim LH	79	Spock Drum
50	Snare Section Hits	80	Spock Drum Rim Shot
50	Snare Drum	81	Tenors High Rims
51	Snare Section Rims	82	Tenors Low Rims
52	Snare Section Rim Shots	83	Stick Click
52	Snare Rim Shot	84	Crash Cymbal
53	Snare Guz Short	85	China Cymbal
54	Snare Guz Long	86	Cowbell
55	Snare Rim Shot (Both Hands)	87	Low Agogo
56	Snare Rim Shot LH	88	High Agogo
57	Snare Section Cross Shots	89	Claves
57	Snare Cross Shots	90	Vibraslap
58	Snare Section Rim Shots (Both Hands)	91	Tambourine
59	Stick Clicks	92	Cabasa
59	Snare Section Cross Sticks	93	Conga Dead Stroke
59	Snare Cross Stick	94	Conga
60	Snare Section Buzz Rolls	95	Conga Bass Tone
60	Snare Buzz Roll	96	Kick Drum (2)
60	Snare Roll	97	Triangle Mute
61	Ride Bell	98	Triangle Open
62	Ride Cymbal	99	Whistle Short
63	Hi-Hat Open	100	Whistle Long
64	Hi-Hat Closed	101	Large Gong
65	Low Tom		

Orchestral Percussion

MIDI Note Number	Note Type	MIDI Note Number	Note Type
27	Hi-Hat Closed	64	Tumba
28	Hi-Hat Foot Splash	65	High Timbale
29	Hi-Hat Open	66	Low Timbale
30	Ride Cymbal	67	High Agogo
31	Stick Click	68	Low Agogo
34	Snare Cross Stick	69	Cabasa
35	Kick Drum	70	Maracas
36	Bass Drum	71	Whistle Short
37	Bass Drum LH	72	Whistle Long
38	Snare Drum	73	Guiro Short
39	Castanets	74	Guiro Long
40	Snare Drum LH	75	Claves
54	Tambourine	76	High Woodblock
55	Splash Cymbal	77	Low Woodblock
56	Cowbell	78	Cuica High
57	Crash Cymbal 2	79	Cuica Low
58	Crash Cymbal	80	Triangle Mute
59	Ride Cymbal 2	81	Triangle Open
60	High Bongo	82	Shaker
61	Low Bongo	83	Sleigh Bell
62	Conga Dead Stroke	84	Bell Tree
63	Conga		