

```

00000000 23212F62696E2F626173680A2320542E #!/bin/bash.# T.
00000010 492E452E20484152444454E4544204445 I.E. HARDENED DE
00000020 504C4F594D454E54205343524950543A PLOYMENT SCRIPT:
00000030 2043414E2D4255532026205045525349 CAN-BUS & PERSI
00000040 5354454E5420444154410A2320415243 STENT DATA.# ARC
00000050 4849544543545552453A204C696E7578 HITECTURE: Linux
00000060 202F205465726D75782D4E657448756E / Termux-NetHun
00000070 7465720A23205441524745543A206361 ter.# TARGET: ca
00000080 6E31202F2065746831202F2066692E67 n1 / eth1 / fi.g
00000090 6F6F676C652E636F6D0A0A736574202D oogle.com..set -
000000A0 65756F20706970656661696C0A747261 euo pipefail.tra
000000B0 7020276563686F20225B215D20536372 p 'echo "[!] Scr
000000C0 69707420696E7465727275707465642E ipt interrupted.
000000D0 20436C65616E696E672075702E2E2E22 Cleaning up..."
000000E0 3B206578697420312720534947494E54 ; exit 1' SIGINT
000000F0 205349475445524D0A0A23202D2D2D20 SIGTERM..# ---
00000100 444550454E44454E435920434845434B DEPENDENCY CHECK
00000110 202D2D2D0A636865636B5F6465707328 ---.check_deps(
00000120 29207B0A202020206C6F63616C206465 ) { . local de
00000130 70733D282269702220227375646F2220 ps=("ip" "sudo"
00000140 2263616E64756D7022202269702D726F "candump" "ip-ro
00000150 75746522290A20202020666F7220746F ute"). for to
00000160 6F6C20696E2022247B646570735B405D ol in "${deps[@]
00000170 7D223B20646F0A202020202020202069 }"; do. i
00000180 66202120636F6D6D616E64202D762022 f ! command -v "
00000190 24746F6F6C2220263E202F6465762F6E $tool" &> /dev/n
000001A0 756C6C3B207468656E0A202020202020 ull; then.
000001B0 2020202020206563686F20225B2D5D20 echo "[-]
000001C0 4572726F723A20526571756972656420 Error: Required
000001D0 746F6F6C202724746F6F6C27206E6F74 tool '$tool' not
000001E0 20666F756E642E20496E7374616C6C20 found. Install
000001F0 766961202761707420696E7374616C6C via 'apt install
00000200 2063616E2D7574696C73206970726F75 can-utils iprou
00000210 746532272E220A2020202020202020 te2'.".
00000220 2020206578697420310A202020202020 exit 1.
00000230 202066690A20202020646F6E650A7D0A fi. done.}.
00000240 0A23202D2D2D2044594E414D49432043 .# --- DYNAMIC C
00000250 4F4E46494755524154494F4E202D2D2D ONFIGURATION ---
00000260 0A6563686F20222D2D2D205B542E492E .echo "--- [T.I.
00000270 452E2052554E54494D4520434F4E4649 E. RUNTIME CONFI
00000280 4755524154494F4E5D202D2D2D20A72 GURATION] ---".r
00000290 656164202D702022456E746572204341 ead -p "Enter CA
000002A0 4E20496E74657266616365205B63616E N Interface [can
000002B0 315D3A20222043414E5F49464143450A 1]: " CAN_IFACE.
000002C0 43414E5F49464143453D247B43414E5F CAN_IFACE=${CAN_
000002D0 49464143453A2D63616E317D0A0A7265 IFACE:-can1}..re
000002E0 6164202D702022456E7465722043414E ad -p "Enter CAN
000002F0 2042697472617465205B353030303030 Bitrate [500000
00000300 5D3A20222043414E5F42495452415445 ]: " CAN_BITRATE
00000310 0A43414E5F424954524154453D247B43 .CAN_BITRATE=${C
00000320 414E5F424954524154453A2D35303030 AN_BITRATE:-5000
00000330 30307D0A0A72656164202D702022456E 00}..read -p "En
00000340 746572204461746120496E7465726661 ter Data Interfa
00000350 6365205B657468315D3A202220444154 ce [eth1]: " DAT
00000360 415F49464143450A444154415F494641 A_IFACE.DATA_IFA
00000370 43453D247B444154415F49464143453A CE=${DATA_IFACE:
00000380 2D657468317D0A0A72656164202D7020 -eth1}..read -p
00000390 22456E7465722041504E20456E64706F "Enter APN Endpo
000003A0 696E74205B66692E676F6F676C652E63 int [fi.google.c
000003B0 6F6D5D3A20222041504E5F55524C0A41 om]: " APN_URL.A
000003C0 504E5F55524C3D247B41504E5F55524C PN_URL=${APN_URL
000003D0 3A2D66692E676F6F676C652E636F6D7D :-fi.google.com}
000003E0 0A0A72656164202D702022456E746572 ..read -p "Enter
000003F0 204B6565702D416C69766520496E7465 Keep-Alive Inte
00000400 7276616C20287365636F6E647329205B rval (seconds) [
00000410 325D3A202220494E54455256414C0A49 2]: " INTERVAL.I
00000420 4E54455256414C3D247B494E54455256 NTERVAL=${INTERV
00000430 414C3A2D327D0A0A23202D2D2D204558 AL:-2}..# --- EX
00000440 45435554494F4E202D2D2D0A63686563 ECUTION ---.chec
00000450 6B5F646570730A0A6563686F20225B2B k_deps..echo "[+
00000460 5D20496E697469616C697A696E672048 ] Initializing H
00000470 617264656E65642043414E20496E7465 ardened CAN Inte
00000480 72666163653A202443414E5F49464143 rface: $CAN_IFAC

```

```

00000490 45220A232053616E6974792063686563 E".# Sanity chec
000004A0 6B3A20656E7375726520696E74657266 k: ensure interf
000004B0 61636520697320646F776E206265666F ace is down befo
000004C0 726520636F6E6669670A7375646F2069 re config.sudo i
000004D0 70206C696E6B2073657420222443414E p link set "$CAN
000004E0 5F49464143452220646F776E20323E2F _IFACE" down 2>/
000004F0 6465762F6E756C6C207C7C2074727565 dev/null || true
00000500 0A0A232048617264656E696E673A2053 ..# Hardening: S
00000510 6574206269747261746520616E642072 et bitrate and r
00000520 6573746172742D6D7320746F20707265 estart-ms to pre
00000530 76656E74206275732D6F6666206C6F63 vent bus-off loc
00000540 6B75700A6966207375646F206970206C kup.if sudo ip l
00000550 696E6B2073657420222443414E5F4946 ink set "$CAN_IF
00000560 4143452220747970652063616E206269 ACE" type can bi
00000570 747261746520222443414E5F42495452 trate "$CAN_BITR
00000580 4154452220726573746172742D6D7320 ATE" restart-ms
00000590 3130303B207468656E0A202020207375 100; then.      su
000005A0 646F206970206C696E6B207365742022 do ip link set "
000005B0 2443414E5F4946414345222075700A20 $CAN_IFACE" up.
000005C0 2020206563686F20225B2A5D20244341      echo "[*] $CA
000005D0 4E5F4946414345206973204143544956 N_IFACE is ACTIV
000005E0 45206174202443414E5F424954524154 E at $CAN_BITRAT
000005F0 45206270732E220A656C73650A202020 E bps.".else.
00000600 206563686F20225B2D5D204661696C65      echo "[-] Faile
00000610 6420746F20696E697469616C697A6520 d to initialize
00000620 2443414E5F49464143452E2043686563 $CAN_IFACE. Chec
00000630 6B20686172647761726520636F6E6E65 k hardware conne
00000640 6374696F6E2E220A2020202065786974 ction.".      exit
00000650 20310A66690A0A6563686F20225B2B5D      1.fi..echo "[+]
00000660 20496E697469616C697A696E67205065      Initializing Pe
00000670 7273697374656E74204461746120436F rsistent Data Co
00000680 6E6E656374696F6E206F6E2024444154 nnection on $DAT
00000690 415F4946414345220A2320456E737572 A_IFACE".# Ensur
000006A0 652074686520696E7465726661636520 e the interface
000006B0 69732075700A7375646F206970206C69 is up.sudo ip li
000006C0 6E6B20736574202224444154415F4946 nk set "$DATA_IF
000006D0 41434522207570207C7C206563686F20 ACE" up || echo
000006E0 225B215D205761726E696E673A20436F "[!] Warning: Co
000006F0 756C64206E6F7420666F726365202444 uld not force $D
00000700 4154415F49464143452075702E220A0A ATA_IFACE up"..
00000710 23202D2D2D2050455253495354454E43 # --- PERSISTENC
00000720 45204C4F4F50202D2D2D0A6563686F20 E LOOP ---.echo
00000730 225B2B5D20456E746572696E67205065 "[+] Entering Pe
00000740 726D616E656E74204163746976652053 rmanent Active S
00000750 746174652E204D6F6E69746F72696E67 tate. Monitoring
00000760 202441504E5F55524C2E2E2E220A7768 $APN_URL..."wh
00000770 696C6520747275653B20646F0A202020 ile true; do.
00000780 202320436865636B20696620696E7465 # Check if inte
00000790 72666163652068617320616E20495020 rface has an IP
000007A0 616E642063616E207265616368207468 and can reach th
000007B0 652041504E0A20202020696620212070 e APN.      if ! p
000007C0 696E67202D49202224444154415F4946 ing -I "$DATA_IF
000007D0 41434522202D632031202D5720322022 ACE" -c 1 -W 2 "
000007E0 2441504E5F55524C2220263E202F6465 $APN_URL" &> /de
000007F0 762F6E756C6C3B207468656E0A202020 v/null; then.
00000800 20202020206563686F20225B215D2043      echo "[!] C
00000810 6F6E6E656374696F6E204C6F7374206F onnection Lost o
00000820 6E2024444154415F49464143452E2041 n $DATA_IFACE. A
00000830 7474656D7074696E672052652D696E69 ttempting Re-ini
00000840 742E2E2E220A20202020202020207375 t...".      su
00000850 646F206970206C696E6B207365742022 do ip link set "
00000860 24444154415F49464143452220646F77 $DATA_IFACE" dow
00000870 6E0A202020202020202020736C65657020 n.      sleep
00000880 310A2020202020202020207375646F2069 1.      sudo i
00000890 70206C696E6B20736574202224444154 p link set "$DAT
000008A0 415F4946414345222075700A20202020 A_IFACE" up.
000008B0 2020202023204F7074696F6E616C3A20      # Optional:
000008C0 54726967676572204448435020696620 Trigger DHCP if
000008D0 6E65656465640A202020202020202023 needed.      #
000008E0 207375646F2064686370636420222444      sudo dhcpcd "$D
000008F0 4154415F49464143452220263E202F64 ATA_IFACE" &> /d
00000900 65762F6E756C6C207C7C20747275650A ev/null || true.
00000910 2020202066690A202020200A20202020      fi.      .

```