LVLHFrameModel

5.1

Generated by Doxygen 1.8.14

## **Contents**

1	Mod	ule Index	1
	1.1	Modules	1
2	Nam	espace Index	3
	2.1	Namespace List	3
3	Data	Structure Index	5
	3.1	Data Structures	5
4	File	Index	7
	4.1	File List	7
5	Mod	ule Documentation	9
	5.1	Models	9
		5.1.1 Detailed Description	9
	5.2	Utils	0
		5.2.1 Detailed Description	0
	5.3	LvlhFrame	1
		5.3.1 Detailed Description	11
		5.3.2 Macro Definition Documentation	11
		5.3.2.1 PATH	1
6	Nam	espace Documentation	13
	6.1	jeod Namespace Reference	13
		6.1.1 Detailed Description	13

ii CONTENTS

7	Data	a Struct	ure Docur	mentation	15
	7.1	jeod::L	vlhFrame	Class Reference	15
		7.1.1	Detailed	Description	16
		7.1.2	Construc	ctor & Destructor Documentation	16
			7.1.2.1	LvlhFrame() [1/2]	16
			7.1.2.2	~LvIhFrame()	16
			7.1.2.3	LvlhFrame() [2/2]	17
		7.1.3	Member	Function Documentation	17
			7.1.3.1	compute_lvlh_frame()	17
			7.1.3.2	initialize()	17
			7.1.3.3	operator=()	18
			7.1.3.4	set_planet()	18
			7.1.3.5	set_planet_name()	18
			7.1.3.6	set_subject_frame()	18
			7.1.3.7	set_subject_name()	19
			7.1.3.8	update()	19
		7.1.4	Friends A	And Related Function Documentation	19
			7.1.4.1	init_attrjeodLvlhFrame	19
			7.1.4.2	InputProcessor	20
		7.1.5	Field Doo	cumentation	20
			7.1.5.1	frame	20
			7.1.5.2	local_dm	20
			7.1.5.3	planet_centered_inertial	20
			7.1.5.4	planet_name	21
			7.1.5.5	subject_frame	21
			7.1.5.6	subject_name	21
	7.2	jeod::L	.vlhFrame <b>N</b>	Messages Class Reference	21
		7.2.1	Detailed	Description	22
		7.2.2	Construc	ctor & Destructor Documentation	22
			7.2.2.1	LvlhFrameMessages() [1/2]	22

CONTENTS

			<b>7.2.2.2</b> LvlhFrameMessages() [2/2]	23
		7.2.3	Member Function Documentation	23
			7.2.3.1 operator=()	23
		7.2.4	Friends And Related Function Documentation	23
			7.2.4.1 init_attrjeodLvlhFrameMessages	23
			7.2.4.2 InputProcessor	23
		7.2.5	Field Documentation	23
			7.2.5.1 divide_by_zero	23
			7.2.5.2 fatal_error	24
			7.2.5.3 illegal_value	24
			7.2.5.4 invalid_configuration	24
			7.2.5.5 invalid_name	24
			7.2.5.6 invalid_object	25
			7.2.5.7 null_pointer	25
			7.2.5.8 trace	25
	7.3	jeod::L	vlhType Class Reference	25
		7.3.1	Detailed Description	26
		7.3.2	Member Enumeration Documentation	26
			7.3.2.1 Type	26
		7.3.3	Constructor & Destructor Documentation	26
			7.3.3.1 LvlhType()	27
		7.3.4	Friends And Related Function Documentation	27
			7.3.4.1 init_attrjeodLvlhType	27
			7.3.4.2 InputProcessor	27
		7.3.5	Field Documentation	27
			7.3.5.1 value	27
8	Eilo	Dogume	entation	29
0	8.1			<b>29</b> 29
	0.1	8.1.1		29 29
	8.2			29 29
	0.2	8.2.1		30
	8.3			30
	0.3	_		
	0.4	8.3.1	·	30
	8.4			30
	0.5	8.4.1	·	31
	8.5			31
		8.5.1	Detailed Description	31
Inc	dex			33

# **Module Index**

## 1.1 Modules

Here is a list of all modules:

Models	 																9
Utils	 							 									 10
LylhFrame																	11

2 Module Index

# Namespace Index

	2.1	Namespace	List
--	-----	-----------	------

Here is a list of all Harriespaces w	itii bilei descriptions.	

jeod																						
	Namespace jeod															 						13

4 Namespace Index

## **Data Structure Index**

## 3.1 Data Structures

Here are the data structures with brief descriptions:

jeod::LvlhFrame	
The class used to represent an LVLH reference frame associated with a subject DynBody	15
jeod::LvlhFrameMessages	
The class that specifies the message IDs used in the LvlhFrame model	21
jeod::LvlhType	
The class used to identify the type of LVLH desired	25

6 Data Structure Index

# File Index

## 4.1 File List

Here is a list of all files with brief descriptions:

lvlh_frame.cc	
Define methods for the LVLH reference frame class	29
lvlh_frame.hh	
Define the class LvlhFrame, the class used to represent a local-vertical, local-horizontal refer-	
ence frame associated with a subject DynBody	29
lvlh_frame_messages.cc	
Implement the class LvIhFrameMessages	30
lvlh_frame_messages.hh	
Define the class LvIhFrameMessages, the class that specifies the message IDs used in the	
LvlhFrame model	30
lvlh_type.hh	
Define the class LylhType, which identifies the type of LVLH desired to be calculated	31

8 File Index

# **Module Documentation**

5.1 Models

Modules

• Utils

5.1.1 Detailed Description

10 Module Documentation

## 5.2 Utils

## Modules

• LvlhFrame

## 5.2.1 Detailed Description

5.3 LvlhFrame 11

## 5.3 LvlhFrame

## **Files**

· file lvlh\_frame.hh

Define the class LvIhFrame, the class used to represent a local-vertical, local-horizontal reference frame associated with a subject DynBody.

· file lvlh\_frame\_messages.hh

Define the class LvlhFrameMessages, the class that specifies the message IDs used in the LvlhFrame model.

· file lvlh\_type.hh

Define the class LvlhType, which identifies the type of LVLH desired to be calculated.

• file lvlh\_frame.cc

Define methods for the LVLH reference frame class.

• file lvlh\_frame\_messages.cc

Implement the class LvlhFrameMessages.

## **Namespaces**

• jeod

Namespace jeod.

#### **Macros**

• #define PATH "utils/lvlh\_frame/"

## 5.3.1 Detailed Description

#### 5.3.2 Macro Definition Documentation

#### 5.3.2.1 PATH

#define PATH "utils/lvlh\_frame/"

Definition at line 30 of file lvlh\_frame\_messages.cc.

12 Module Documentation

# **Namespace Documentation**

## 6.1 jeod Namespace Reference

Namespace jeod.

## **Data Structures**

· class LvlhFrame

The class used to represent an LVLH reference frame associated with a subject DynBody.

class LvlhFrameMessages

The class that specifies the message IDs used in the LvlhFrame model.

class LvlhType

The class used to identify the type of LVLH desired.

## 6.1.1 Detailed Description

Namespace jeod.

## **Data Structure Documentation**

## 7.1 jeod::LvIhFrame Class Reference

The class used to represent an LVLH reference frame associated with a subject DynBody.

```
#include <lvlh_frame.hh>
```

#### **Public Member Functions**

- LvlhFrame ()=default
- ∼LvlhFrame ()

Destruct an LvlhFrame object.

- LvlhFrame (const LvlhFrame &)=delete
- LvIhFrame & operator= (const LvIhFrame &)=delete
- void initialize (DynManager &dyn\_manager)

Begin initialization of an LvlhFrame.

• void update ()

Update the state.

void set\_subject\_name (const std::string &new\_name)

Set the subject\_name to the supplied value.

void set\_planet\_name (const std::string &new\_name)

Set the planet\_name to the supplied value.

void set\_subject\_frame (RefFrame &new\_frame)

Set the subject\_frame to the supplied value.

void set planet (BasePlanet &new planet)

Set the planet whose PCI frame will be the reference for LVLH.

#### **Data Fields**

· RefFrame frame

The LVLH frame defined by the subject frame's motion with respect to the reference planet.

std::string subject\_name {""}

The frame whose motion defines LVLH.

std::string planet\_name {""}

The planet used as reference for the LVLH frame.

## **Protected Member Functions**

• void compute\_lvlh\_frame (const RefFrameTrans &rel\_trans)

Update the state of the LVLH frame wrt its parent.

#### **Protected Attributes**

RefFrame \* subject\_frame {}

The (moving) frame specified with subject\_name.

• RefFrame \* planet\_centered\_inertial {}

The inertial frame with origin at the center of the specified planet.

#### **Private Attributes**

DynManager \* local\_dm {}

A local pointer to the dynamics manager needed for clean-up.

#### **Friends**

- · class InputProcessor
- void init attrjeod LvlhFrame ()

## 7.1.1 Detailed Description

The class used to represent an LVLH reference frame associated with a subject DynBody.

Definition at line 82 of file lvlh\_frame.hh.

#### 7.1.2 Constructor & Destructor Documentation

```
7.1.2.1 LvlhFrame() [1/2]
jeod::LvlhFrame::LvlhFrame ( ) [default]
```

#### 7.1.2.2 $\sim$ LvlhFrame()

```
jeod::LvlhFrame::\sim LvlhFrame ( )
```

Destruct an LvlhFrame object.

Definition at line 49 of file lvlh\_frame.cc.

References frame, local\_dm, planet\_centered\_inertial, and subject\_frame.

#### 7.1.2.3 LvlhFrame() [2/2]

#### 7.1.3 Member Function Documentation

#### 7.1.3.1 compute\_lvlh\_frame()

Update the state of the LVLH frame wrt its parent.

#### **Parameters**

in rel_trans Planet relative st	ate
---------------------------------	-----

Definition at line 240 of file lvlh\_frame.cc.

References frame.

Referenced by update().

#### 7.1.3.2 initialize()

Begin initialization of an LvlhFrame.

#### **Parameters**

in,out	dyn_manager	Dynamics manager

Definition at line 75 of file lvlh\_frame.cc.

References frame, jeod::LvlhFrameMessages::invalid\_configuration, jeod::LvlhFrameMessages::invalid\_name, local\_dm, planet\_centered\_inertial, planet\_name, subject\_frame, and subject\_name.

#### 7.1.3.3 operator=()

## 7.1.3.4 set\_planet()

Set the planet whose PCI frame will be the reference for LVLH.

#### **Parameters**

in <i>new_planet</i> n	ew planet.
------------------------	------------

Definition at line 231 of file lvlh\_frame.cc.

References planet\_centered\_inertial.

## 7.1.3.5 set\_planet\_name()

Set the planet\_name to the supplied value.

#### **Parameters**

in	new_name	new name.
	_	

Definition at line 222 of file lvlh\_frame.cc.

References planet\_name.

## 7.1.3.6 set\_subject\_frame()

Set the subject\_frame to the supplied value.

#### **Parameters**

Definition at line 213 of file lvlh\_frame.cc.

References subject\_frame.

#### 7.1.3.7 set\_subject\_name()

Set the subject\_name to the supplied value.

#### **Parameters**

in	new_name	new name.
----	----------	-----------

Definition at line 204 of file lvlh\_frame.cc.

References subject\_name.

#### 7.1.3.8 update()

```
void jeod::LvlhFrame::update ( )
```

Update the state.

Definition at line 177 of file lvlh\_frame.cc.

References compute\_lvlh\_frame(), frame, planet\_centered\_inertial, and subject\_frame.

#### 7.1.4 Friends And Related Function Documentation

#### 7.1.4.1 init\_attrjeod\_\_LvlhFrame

```
void init_attrjeod__LvlhFrame ( ) [friend]
```

#### 7.1.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 84 of file lvlh\_frame.hh.

#### 7.1.5 Field Documentation

#### 7.1.5.1 frame

```
RefFrame jeod::LvlhFrame::frame
```

The LVLH frame defined by the subject frame's motion with respect to the reference planet.

```
trick_units(-)
```

Definition at line 90 of file lvlh\_frame.hh.

Referenced by compute\_lvlh\_frame(), initialize(), update(), and ~LvlhFrame().

#### 7.1.5.2 local\_dm

```
DynManager* jeod::LvlhFrame::local_dm {} [private]
```

A local pointer to the dynamics manager needed for clean-up.

```
trick_units(-)
```

Definition at line 117 of file lvlh\_frame.hh.

Referenced by initialize(), and ~LvlhFrame().

#### 7.1.5.3 planet\_centered\_inertial

```
RefFrame* jeod::LvlhFrame::planet_centered_inertial {} [protected]
```

The inertial frame with origin at the center of the specified planet.

```
trick_units(-)
```

Definition at line 111 of file lvlh\_frame.hh.

Referenced by initialize(), set\_planet(), update(), and  $\sim$ LvlhFrame().

#### 7.1.5.4 planet\_name

```
std::string jeod::LvlhFrame::planet_name {""}
```

The planet used as reference for the LVLH frame.

trick\_units(-)

Definition at line 100 of file lvlh\_frame.hh.

Referenced by initialize(), and set\_planet\_name().

#### 7.1.5.5 subject\_frame

```
RefFrame* jeod::LvlhFrame::subject_frame {} [protected]
```

The (moving) frame specified with subject\_name.

trick\_units(-)

Definition at line 106 of file lvlh\_frame.hh.

Referenced by initialize(), set\_subject\_frame(), update(), and ~LvlhFrame().

#### 7.1.5.6 subject\_name

```
std::string jeod::LvlhFrame::subject_name {""}
```

The frame whose motion defines LVLH.

Can be on a vehicle or not.trick\_units(-)

Definition at line 95 of file lvlh\_frame.hh.

Referenced by initialize(), and set\_subject\_name().

The documentation for this class was generated from the following files:

- lvlh\_frame.hh
- · lvlh\_frame.cc

## 7.2 jeod::LvlhFrameMessages Class Reference

The class that specifies the message IDs used in the LvlhFrame model.

```
#include <lvlh_frame_messages.hh>
```

#### **Public Member Functions**

- LvlhFrameMessages ()=delete
- LvlhFrameMessages (const LvlhFrameMessages &)=delete
- LvlhFrameMessages & operator= (const LvlhFrameMessages &)=delete

#### Static Public Attributes

- static const char \* fatal\_error = "utils/lvlh\_frame/" "fatal\_error"

  Issued when performing an action results in an error return from the method performing the action.
- static const char \* illegal\_value = "utils/lvlh\_frame/" "illegal\_value" Issued when a simple type (e.g.
- static const char \* invalid\_name = "utils/lvlh\_frame/" "invalid\_name"

Issued when a name is invalid (NULL, empty, or does not name an object of the specified type).

- static const char \* invalid\_configuration = "utils/lvlh\_frame/" "invalid\_configuration"
- Issued when insufficient information has been specified prior to initialization.
   static const char \* invalid\_object = "utils/lvlh\_frame/" "invalid\_object"
  - Issued when a pointer points to an object of the wrong type.
- static const char \* null\_pointer = "utils/lvlh\_frame/" "null\_pointer"

Error issued when a pointer is required but was not provided.

- static const char \* trace = "utils/lvlh frame/" "trace"
  - Debug message issued to trace LvlhFrame actions.
- static const char \* divide\_by\_zero = "utils/lvlh\_frame/" "divide\_by\_zero"

Fatal message when a divide by zero is encountered.

#### Friends

- class InputProcessor
- void init\_attrjeod\_\_LvlhFrameMessages ()

## 7.2.1 Detailed Description

The class that specifies the message IDs used in the LvlhFrame model.

Definition at line 81 of file lvlh\_frame\_messages.hh.

#### 7.2.2 Constructor & Destructor Documentation

#### 7.2.2.1 LvlhFrameMessages() [1/2]

```
jeod::LvlhFrameMessages::LvlhFrameMessages ( ) [delete]
```

#### 7.2.2.2 LvlhFrameMessages() [2/2]

#### 7.2.3 Member Function Documentation

#### 7.2.3.1 operator=()

#### 7.2.4 Friends And Related Function Documentation

#### 7.2.4.1 init\_attrjeod\_\_LvlhFrameMessages

```
void init_attrjeod__LvlhFrameMessages ( ) [friend]
```

#### 7.2.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 83 of file lvlh\_frame\_messages.hh.

#### 7.2.5 Field Documentation

## 7.2.5.1 divide\_by\_zero

```
const char * jeod::LvlhFrameMessages::divide_by_zero = "utils/lvlh_frame/" "divide_by_zero"
[static]
```

Fatal message when a divide by zero is encountered.

```
trick_units(-)
```

Definition at line 126 of file lvlh\_frame\_messages.hh.

#### 7.2.5.2 fatal\_error

```
const char * jeod::LvlhFrameMessages::fatal_error = "utils/lvlh_frame/" "fatal_error" [static]
```

Issued when performing an action results in an error return from the method performing the action.

trick\_units(-)

Definition at line 89 of file lvlh\_frame\_messages.hh.

#### 7.2.5.3 illegal\_value

```
const char * jeod::LvlhFrameMessages::illegal_value = "utils/lvlh_frame/" "illegal_value"
[static]
```

Issued when a simple type (e.g.

an enum) has an illegal value.trick\_units(-)

Definition at line 94 of file lvlh\_frame\_messages.hh.

#### 7.2.5.4 invalid\_configuration

```
\verb|const| char * jeod::LvlhFrameMessages::invalid\_configuration = "utils/lvlh\_frame/" "invalid\_configuration" [static] \\
```

Issued when insufficient information has been specified prior to initialization.

trick\_units(-)

Definition at line 106 of file lvlh\_frame\_messages.hh.

Referenced by jeod::LvlhFrame::initialize().

#### 7.2.5.5 invalid\_name

```
const char * jeod::LvlhFrameMessages::invalid_name = "utils/lvlh_frame/" "invalid_name" [static]
```

Issued when a name is invalid (NULL, empty, or does not name an object of the specified type).

trick\_units(-)

Definition at line 100 of file lvlh\_frame\_messages.hh.

Referenced by jeod::LvlhFrame::initialize().

#### 7.2.5.6 invalid\_object

```
const char * jeod::LvlhFrameMessages::invalid_object = "utils/lvlh_frame/" "invalid_object"
[static]
```

Issued when a pointer points to an object of the wrong type.

```
trick_units(-)
```

Definition at line 111 of file lvlh\_frame\_messages.hh.

#### 7.2.5.7 null\_pointer

```
const char * jeod::LvlhFrameMessages::null_pointer = "utils/lvlh_frame/" "null_pointer" [static]
```

Error issued when a pointer is required but was not provided.

trick\_units(-)

Definition at line 116 of file lvlh\_frame\_messages.hh.

#### 7.2.5.8 trace

```
const char * jeod::LvlhFrameMessages::trace = "utils/lvlh_frame/" "trace" [static]
```

Debug message issued to trace LvlhFrame actions.

trick units(-)

Definition at line 121 of file lvlh frame messages.hh.

The documentation for this class was generated from the following files:

- · IvIh frame messages.hh
- lvlh\_frame\_messages.cc

## 7.3 jeod::LvlhType Class Reference

The class used to identify the type of LVLH desired.

```
#include <lvlh_type.hh>
```

#### **Public Types**

• enum Type { Rectilinear = 0, CircularCurvilinear = 1, EllipticalCurvilinear = 2 }

An enumeration to specify the type of LVLH coordinates to use, whether rectilinear, circular curvilinear, or elliptical curvilinear.

## **Public Member Functions**

• LvlhType ()

Default constructor.

## **Data Fields**

· Type value

Indicates type of LVLH coordinates desired.

## **Friends**

- class InputProcessor
- void init\_attrjeod\_\_LvlhType ()

## 7.3.1 Detailed Description

The class used to identify the type of LVLH desired.

Definition at line 76 of file lvlh\_type.hh.

## 7.3.2 Member Enumeration Documentation

## 7.3.2.1 Type

```
enum jeod::LvlhType::Type
```

An enumeration to specify the type of LVLH coordinates to use, whether rectilinear, circular curvilinear, or elliptical curvilinear.

As of March 2015, elliptical is not implemented.

#### Enumerator

Rectilinear	
CircularCurvilinear	
EllipticalCurvilinear	

Definition at line 85 of file lvlh\_type.hh.

#### 7.3.3 Constructor & Destructor Documentation

#### 7.3.3.1 LvlhType()

```
jeod::LvlhType::LvlhType ( ) [inline]
```

Default constructor.

Definition at line 110 of file lvlh\_type.hh.

## 7.3.4 Friends And Related Function Documentation

## 7.3.4.1 init\_attrjeod\_\_LvlhType

```
void init_attrjeod__LvlhType ( ) [friend]
```

#### 7.3.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 78 of file lvlh\_type.hh.

#### 7.3.5 Field Documentation

#### 7.3.5.1 value

```
Type jeod::LvlhType::value
```

Indicates type of LVLH coordinates desired.

Default is rectilinear.trick\_units(-)

Definition at line 103 of file lvlh\_type.hh.

The documentation for this class was generated from the following file:

• lvlh\_type.hh

## **File Documentation**

## 8.1 lvlh\_frame.cc File Reference

Define methods for the LVLH reference frame class.

```
#include <cstddef>
#include "dynamics/dyn_manager/include/dyn_manager.hh"
#include "environment/planet/include/base_planet.hh"
#include "utils/math/include/vector3.hh"
#include "utils/message/include/message_handler.hh"
#include "utils/named_item/include/named_item.hh"
#include "../include/lvlh_frame.hh"
#include "../include/lvlh_frame_messages.hh"
```

## **Namespaces**

• jeod

Namespace jeod.

#### 8.1.1 Detailed Description

Define methods for the LVLH reference frame class.

## 8.2 lvlh\_frame.hh File Reference

Define the class LvIhFrame, the class used to represent a local-vertical, local-horizontal reference frame associated with a subject DynBody.

```
#include <string>
#include "dynamics/dyn_manager/include/class_declarations.hh"
#include "environment/planet/include/class_declarations.hh"
#include "utils/ref_frames/include/ref_frame.hh"
#include "utils/sim_interface/include/jeod_class.hh"
```

30 File Documentation

#### **Data Structures**

· class jeod::LvlhFrame

The class used to represent an LVLH reference frame associated with a subject DynBody.

## **Namespaces**

· jeod

Namespace jeod.

## 8.2.1 Detailed Description

Define the class LvIhFrame, the class used to represent a local-vertical, local-horizontal reference frame associated with a subject DynBody.

## 8.3 lvlh\_frame\_messages.cc File Reference

Implement the class LvlhFrameMessages.

```
#include "../include/lvlh_frame_messages.hh"
```

#### **Namespaces**

• jeod

Namespace jeod.

#### Macros

• #define PATH "utils/lvlh\_frame/"

#### 8.3.1 Detailed Description

Implement the class LvlhFrameMessages.

## 8.4 lvlh\_frame\_messages.hh File Reference

Define the class LvlhFrameMessages, the class that specifies the message IDs used in the LvlhFrame model.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

#### **Data Structures**

• class jeod::LvlhFrameMessages

The class that specifies the message IDs used in the LvlhFrame model.

## **Namespaces**

• jeod

Namespace jeod.

## 8.4.1 Detailed Description

Define the class LvlhFrameMessages, the class that specifies the message IDs used in the LvlhFrame model.

## 8.5 lvlh\_type.hh File Reference

Define the class LvlhType, which identifies the type of LVLH desired to be calculated.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

## **Data Structures**

· class jeod::LvIhType

The class used to identify the type of LVLH desired.

## **Namespaces**

• jeod

Namespace jeod.

#### 8.5.1 Detailed Description

Define the class LvIhType, which identifies the type of LVLH desired to be calculated.

32 File Documentation

# Index

$\sim$ LvlhFrame	set_subject_name, 19
jeod::LvlhFrame, 16	subject_frame, 21
	subject_name, 21
compute_lvlh_frame	update, 19
jeod::LvIhFrame, 17	jeod::LvIhFrameMessages, 21
allocation to the second	divide_by_zero, 23
divide_by_zero	fatal_error, 23
jeod::LvlhFrameMessages, 23	illegal_value, 24
fatal error	init_attrjeodLvlhFrameMessages, 23
jeod::LvlhFrameMessages, 23	InputProcessor, 23
frame	invalid_configuration, 24
jeod::LvlhFrame, 20	invalid_name, 24
joodEviin raino, Eo	invalid_object, 24
illegal_value	LvlhFrameMessages, 22
jeod::LvlhFrameMessages, 24	null_pointer, 25
init_attrjeodLvlhFrame	operator=, 23
jeod::LvlhFrame, 19	trace, 25
init_attrjeodLvlhFrameMessages	jeod::LvIhType, 25
jeod::LvlhFrameMessages, 23	init_attrjeodLvlhType, 27
init_attrjeodLvlhType	InputProcessor, 27
jeod::LvlhType, 27	LvlhType, 26
initialize	Type, 26
jeod::LvIhFrame, 17	value, 27
InputProcessor	
jeod::LvlhFrame, 19	local_dm
jeod::LvlhFrameMessages, 23	jeod::LvlhFrame, 20
jeod::LvlhType, 27	lvlh_frame.cc, 29
invalid_configuration	lvlh_frame.hh, 29
jeod::LvlhFrameMessages, 24	lvlh_frame_messages.cc, 30
invalid_name	lvlh_frame_messages.hh, 30
jeod::LvIhFrameMessages, 24	lvlh_type.hh, 31
invalid_object	LvlhFrame, 11
jeod::LvlhFrameMessages, 24	jeod::LvlhFrame, 16
Jeeun am am am an agus, a r	PATH, 11
jeod, 13	LvlhFrameMessages
jeod::LvlhFrame, 15	jeod::LvlhFrameMessages, 22
$\sim$ LvIhFrame, 16	LvlhType
compute_lvlh_frame, 17	jeod::LvlhType, <mark>26</mark>
frame, 20	
init_attrjeodLvlhFrame, 19	Models, 9
initialize, 17	null_pointer
InputProcessor, 19	jeod::LvlhFrameMessages, 25
local_dm, 20	jeouEviili Tailieiviessages, 25
LvIhFrame, 16	operator=
operator=, 17	jeod::LvlhFrame, 17
planet_centered_inertial, 20	jeod::LvlhFrameMessages, 23
planet_name, 20	,
set_planet, 18	PATH
set_planet_name, 18	LvlhFrame, 11
set_subject_frame, 18	planet_centered_inertial

34 INDEX

```
jeod::LvlhFrame, 20
planet_name
    jeod::LvlhFrame, 20
set_planet
    jeod::LvlhFrame, 18
set_planet_name
    jeod::LvlhFrame, 18
set_subject_frame
    jeod::LvlhFrame, 18
set_subject_name
    jeod::LvlhFrame, 19
subject_frame
    jeod::LvlhFrame, 21
subject_name
    jeod::LvlhFrame, 21
trace
    jeod::LvlhFrameMessages, 25
Type
    jeod::LvlhType, 26
update
    jeod::LvlhFrame, 19
Utils, 10
value
    jeod::LvlhType, 27
```