ThermalModel

5.1

Generated by Doxygen 1.8.14

Contents

1	Mod	odule Index	1
	1.1	1 Modules	 1
2	Nam	amespace Index	3
	2.1	1 Namespace List	 3
3	Hier	ierarchical Index	5
	3.1	1 Class Hierarchy	 5
4	Data	ata Structure Index	7
	4.1	1 Data Structures	 7
5	File	le Index	9
	5.1	1 File List	 9
6	Mod	odule Documentation	11
	6.1	1 Models	 11
		6.1.1 Detailed Description	 11
	6.2	2 Interactions	 12
		6.2.1 Detailed Description	 12
	6.3	3 ThermalRider	 13
		6.3.1 Detailed Description	 13
		6.3.2 Macro Definition Documentation	 13
		6.3.2.1 PATH	 13

ii CONTENTS

7	Nam	espace	Documer	ntation	15
	7.1	jeod Na	amespace	Reference	15
		7.1.1	Detailed	Description	15
8	Data	Structi	ure Docun	nentation	17
	8.1	jeod::T	hermalFac	cetRider Class Reference	17
		8.1.1	Detailed	Description	18
		8.1.2	Construc	tor & Destructor Documentation	18
			8.1.2.1	ThermalFacetRider() [1/2]	18
			8.1.2.2	\sim ThermalFacetRider()	19
			8.1.2.3	ThermalFacetRider() [2/2]	19
		8.1.3	Member	Function Documentation	19
			8.1.3.1	accumulate_thermal_sources()	19
			8.1.3.2	initialize()	19
			8.1.3.3	integrate()	20
			8.1.3.4	operator=()	20
		8.1.4	Friends A	and Related Function Documentation	20
			8.1.4.1	init_attrjeodThermalFacetRider	20
			8.1.4.2	InputProcessor	20
		8.1.5	Field Doo	cumentation	20
			8.1.5.1	active	21
			8.1.5.2	cycle_time	21
			8.1.5.3	d_temperature	21
			8.1.5.4	dynamic_temperature	21
			8.1.5.5	emissivity	22
			8.1.5.6	facet	22
			8.1.5.7	heat_capacity	22
			8.1.5.8	integrable_object	22
			8.1.5.9	next_temperature	23
			8.1.5.10	power_absorb	23
			8.1.5.11	power_emit	23

CONTENTS

		8.1.5.12	rad_constant	23
		8.1.5.13	stefan_boltzmann	24
		8.1.5.14	thermal_power_dump	24
8.2	jeod::T	hermalInte	egrableObject Class Reference	24
	8.2.1	Detailed	Description	26
	8.2.2	Construc	etor & Destructor Documentation	26
		8.2.2.1	ThermalIntegrableObject() [1/2]	26
		8.2.2.2	~ThermalIntegrableObject()	26
		8.2.2.3	ThermalIntegrableObject() [2/2]	26
	8.2.3	Member	Function Documentation	26
		8.2.3.1	compute_temp_dot()	27
		8.2.3.2	create_integrators()	27
		8.2.3.3	destroy_integrators()	27
		8.2.3.4	get_temp()	28
		8.2.3.5	get_temp_dot()	28
		8.2.3.6	initialize()	28
		8.2.3.7	integrate()	29
		8.2.3.8	operator=()	29
		8.2.3.9	reset_integrators()	29
	8.2.4	Friends A	And Related Function Documentation	29
		8.2.4.1	init_attrjeodThermalIntegrableObject	29
		8.2.4.2	InputProcessor	30
	8.2.5	Field Doo	cumentation	30
		8.2.5.1	active	30
		8.2.5.2	integrator	30
		8.2.5.3	rider	30
		8.2.5.4	t_pow4	31
		8.2.5.5	temp	31
		8.2.5.6	temp_dot	31
8.3	jeod::T	hermalMe	essages Class Reference	31

iv CONTENTS

	8.3.1	Detailed	Description	32
	8.3.2	Construc	stor & Destructor Documentation	32
		8.3.2.1	ThermalMessages() [1/2]	32
		8.3.2.2	ThermalMessages() [2/2]	32
	8.3.3	Member	Function Documentation	32
		8.3.3.1	operator=()	33
	8.3.4	Friends A	And Related Function Documentation	33
		8.3.4.1	init_attrjeodThermalMessages	33
		8.3.4.2	InputProcessor	33
	8.3.5	Field Doo	cumentation	33
		8.3.5.1	incomplete_setup_error	33
		8.3.5.2	invalid_integration_operation	34
8.4	jeod::T	hermalMo	delRider Class Reference	34
	8.4.1	Detailed	Description	34
	8.4.2	Construc	stor & Destructor Documentation	35
		8.4.2.1	ThermalModelRider() [1/2]	35
		8.4.2.2	\sim ThermalModelRider()	35
		8.4.2.3	ThermalModelRider() [2/2]	35
	8.4.3	Member	Function Documentation	35
		8.4.3.1	operator=()	35
		8.4.3.2	update()	35
	8.4.4	Friends A	And Related Function Documentation	36
		8.4.4.1	init_attrjeodThermalModelRider	36
		8.4.4.2	InputProcessor	36
	8.4.5	Field Doo	cumentation	36
		8.4.5.1	active	36
		8.4.5.2	include_internal_thermal_effects	36
8.5	jeod::T	hermalPar	rams Class Reference	37
	8.5.1	Detailed	Description	37
	8.5.2	Construc	stor & Destructor Documentation	37
		8.5.2.1	ThermalParams() [1/2]	37
		8.5.2.2	~ThermalParams()	38
		8.5.2.3	ThermalParams() [2/2]	38
	8.5.3	Member	Function Documentation	38
		8.5.3.1	operator=()	38
	8.5.4	Friends A	And Related Function Documentation	38
		8.5.4.1	init_attrjeodThermalParams	38
		8.5.4.2	InputProcessor	38
	8.5.5	Field Doo	cumentation	38
		8.5.5.1	emissivity	39
		8.5.5.2	heat_capacity_per_area	39
		8.5.5.3	thermal_power_dump	39

CONTENTS

9	File I	Documen	atation	41
	9.1	class_de	clarations.hh File Reference	41
		9.1.1	Detailed Description	41
	9.2	thermal_	facet_rider.cc File Reference	41
		9.2.1	Detailed Description	42
		9.2.2 N	Macro Definition Documentation	42
		9	9.2.2.1 pow4	42
	9.3	thermal_	facet_rider.hh File Reference	42
		9.3.1	Detailed Description	42
	9.4	thermal_	integrable_object.cc File Reference	43
		9.4.1	Detailed Description	43
	9.5	thermal_	integrable_object.hh File Reference	43
		9.5.1	Detailed Description	43
	9.6	thermal_	messages.cc File Reference	44
		9.6.1	Detailed Description	44
	9.7	thermal_	messages.hh File Reference	44
		9.7.1	Detailed Description	44
	9.8	thermal_	model_rider.cc File Reference	45
		9.8.1	Detailed Description	45
	9.9	thermal_	model_rider.hh File Reference	45
		9.9.1	Detailed Description	45
	9.10	thermal_	params.hh File Reference	45
		9.10.1	Detailed Description	46
Inc	lex			47

Module Index

1.1 Modules

Here is a list of all modules:

Models	11
Interactions	 12
ThermalRider	 13

2 Module Index

Namespace Index

2.1	Namespace	List

riere is a list of all flamespaces with brief t	descriptions.	
jeod		

4 Namespace Index

Hierarchical Index

3.1 Class Hierarchy

This inheritance list is sorted roughly, but not completely, alphabetically:

ntegrableObject	
jeod::ThermalIntegrableObject	24
eod::ThermalFacetRider	17
eod::ThermalMessages	31
eod::ThermalModelRider	34
eod::ThermalParams	37

6 Hierarchical Index

Data Structure Index

4.1 Data Structures

Here are the data structures with brief descriptions:

jeod::ThermalFacetRider	
Defining the thermal characteristics of surface facets	17
jeod::ThermalIntegrableObject	
Encapsulates a thermal integrator for a facet	24
jeod::ThermalMessages	
Specifying the message IDs used in the model	31
jeod::ThermalModelRider	
Defining the thermal functionality	34
jeod::ThermalParams	
A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-	
model facets in their respective InteractionSurfaceFactorys	37

8 Data Structure Index

File Index

5.1 File List

Here is a list of all files with brief descriptions:

class_declarations.hh	
Forward declaration of classes defined in Thermal_rider model	41
thermal_facet_rider.cc	
ThermalFacetRider interaction model	41
thermal_facet_rider.hh	
Defining the thermal characteristics of surface facets	42
thermal_integrable_object.cc	
Encapsulates an integrator for a single facet	43
thermal_integrable_object.hh	
Define an IntegrableObject class adapted to thermal integration	43
thermal_messages.cc	
Implement the class ThermalMessages	44
thermal_messages.hh	
Define the class ThermalMessages, the class that specifies the message IDs used in the model	44
thermal_model_rider.cc	
ThermalModelRider interaction model	45
thermal_model_rider.hh	
Defining the thermal functionality	45
thermal_params.hh	
A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-	
model facets in their respective InteractionSurfaceFactorys	45

10 File Index

Module Documentation

6.1 Models

Modules

Interactions

6.1.1 Detailed Description

12 Module Documentation

6.2 Interactions

Modules

• ThermalRider

6.2.1 Detailed Description

6.3 ThermalRider 13

6.3 ThermalRider

Files

· file class declarations.hh

Forward declaration of classes defined in Thermal_rider model.

• file thermal_facet_rider.hh

Defining the thermal characteristics of surface facets.

• file thermal_integrable_object.hh

Define an IntegrableObject class adapted to thermal integration.

• file thermal_messages.hh

Define the class ThermalMessages, the class that specifies the message IDs used in the model.

• file thermal_model_rider.hh

Defining the thermal functionality.

· file thermal_params.hh

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

· file thermal_facet_rider.cc

ThermalFacetRider interaction model.

• file thermal_integrable_object.cc

Encapsulates an integrator for a single facet.

file thermal_messages.cc

Implement the class ThermalMessages.

• file thermal_model_rider.cc

ThermalModelRider interaction model.

Namespaces

jeod

Namespace jeod.

Macros

• #define PATH "utils/thermal rider/"

6.3.1 Detailed Description

6.3.2 Macro Definition Documentation

6.3.2.1 PATH

```
#define PATH "utils/thermal_rider/"
```

Definition at line 35 of file thermal_messages.cc.

14 Module Documentation

Namespace Documentation

7.1 jeod Namespace Reference

Namespace jeod.

Data Structures

· class ThermalFacetRider

Defining the thermal characteristics of surface facets.

class ThermalIntegrableObject

Encapsulates a thermal integrator for a facet.

· class ThermalMessages

Specifying the message IDs used in the model.

• class ThermalModelRider

Defining the thermal functionality.

• class ThermalParams

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

7.1.1 Detailed Description

Namespace jeod.

Data Structure Documentation

8.1 jeod::ThermalFacetRider Class Reference

Defining the thermal characteristics of surface facets.

```
#include <thermal_facet_rider.hh>
```

Public Member Functions

- ThermalFacetRider ()=default
- virtual \sim ThermalFacetRider ()=default
- ThermalFacetRider & operator= (const ThermalFacetRider &)=delete
- ThermalFacetRider (const ThermalFacetRider &)=delete
- void initialize (double temperature, double surface area)

Initialize the thermal aspects of the facet.

• void accumulate_thermal_sources ()

Collects together all surface and internal thermal sources that affect a facet.

· double integrate ()

Runge-Kutta 4th order integration of the temperature variation.

Data Fields

```
• double d_temperature {}
```

Change in temperature.

double power_absorb {}

Rate at which energy is absorbed from the environment, vehicle, and surface.

double power_emit {}

Rate at which energy is thermally radiated from the facet.

double heat_capacity {}

Heat capacity of the facet.

double rad_constant {}

Combination of variables that are held constant for any given facet.

InteractionFacet * facet {}

Pointer back to facet that contains this thermal rider.

bool active {true}

Flag set to indicate whether the facet to which this rider is attached has a dynamic temperature variability.

double thermal_power_dump {}

Rate at which thermal energy is transfered to the facet from within the vehicle.

· double emissivity {}

Fraction of sigma- T^{\wedge} 4 (potential for emissive radiation) that is actually emitted.

ThermalIntegrableObject integrable_object

The encapsulation of a first order integrator which can optionally be used to integrate the temperature.

Static Public Attributes

• static double cycle_time = 0.0

Time since the last temperature calculation for the particular model under consideration.

Static Protected Attributes

static const double stefan_boltzmann = 5.6704004E-08
 Stefan-Boltzmann constant.

Private Attributes

• double next_temperature {}

The predicted value of temperature at the next time-step.

• double dynamic_temperature {}

The dynamic value of the facet kinetic temperature.

Friends

- · class InputProcessor
- void init_attrjeod__ThermalFacetRider ()

8.1.1 Detailed Description

Defining the thermal characteristics of surface facets.

Definition at line 83 of file thermal_facet_rider.hh.

8.1.2 Constructor & Destructor Documentation

8.1.2.1 ThermalFacetRider() [1/2]

```
jeod::ThermalFacetRider::ThermalFacetRider ( ) [default]
```

8.1.2.2 ∼ThermalFacetRider()

```
\verb|virtual| jeod:: ThermalFacetRider:: \sim ThermalFacetRider ( ) [virtual], [default]|
```

8.1.2.3 ThermalFacetRider() [2/2]

8.1.3 Member Function Documentation

8.1.3.1 accumulate_thermal_sources()

```
void jeod::ThermalFacetRider::accumulate_thermal_sources ( )
```

Collects together all surface and internal thermal sources that affect a facet.

Definition at line 60 of file thermal_facet_rider.cc.

References power_absorb, power_emit, and thermal_power_dump.

8.1.3.2 initialize()

Initialize the thermal aspects of the facet.

Parameters

in	temperature	temperature of facet Units: K
in	surface_area	area of facet surface
		Units: M*M

Definition at line 108 of file thermal facet rider.cc.

References dynamic_temperature, emissivity, jeod::ThermalMessages::incomplete_setup_error, jeod::Thermal longrableObject::initialize(), integrable_object, next_temperature, rad_constant, and stefan_boltzmann.

8.1.3.3 integrate()

```
double jeod::ThermalFacetRider::integrate ( )
```

Runge-Kutta 4th order integration of the temperature variation.

Returns

void

Definition at line 160 of file thermal_facet_rider.cc.

References active, cycle_time, d_temperature, dynamic_temperature, heat_capacity, jeod::ThermalMessages ::invalid_integration_operation, next_temperature, pow4, power_absorb, power_emit, and rad_constant.

8.1.3.4 operator=()

8.1.4 Friends And Related Function Documentation

8.1.4.1 init_attrjeod__ThermalFacetRider

```
void init_attrjeod__ThermalFacetRider ( ) [friend]
```

8.1.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 85 of file thermal_facet_rider.hh.

8.1.5 Field Documentation

8.1.5.1 active

```
bool jeod::ThermalFacetRider::active {true}
```

Flag set to indicate whether the facet to which this rider is attached has a dynamic temperature variability.

trick_units(-)

Definition at line 134 of file thermal_facet_rider.hh.

Referenced by integrate().

8.1.5.2 cycle_time

```
double jeod::ThermalFacetRider::cycle_time = 0.0 [static]
```

Time since the last temperature calculation for the particular model under consideration.

trick_units(s)

Definition at line 91 of file thermal_facet_rider.hh.

Referenced by integrate(), and jeod::ThermalModelRider::update().

8.1.5.3 d_temperature

```
double jeod::ThermalFacetRider::d_temperature {}
```

Change in temperature.

trick_units(-)

Definition at line 96 of file thermal_facet_rider.hh.

Referenced by integrate().

8.1.5.4 dynamic_temperature

```
double jeod::ThermalFacetRider::dynamic_temperature {} [private]
```

The dynamic value of the facet kinetic temperature.

THIS VALUE IS USED ONLY BY THE THERMAL INTEGRATOR, AND SHOULD NOT BE SET EXTERNALLY. \leftarrow trick_units(K)

Definition at line 175 of file thermal_facet_rider.hh.

Referenced by initialize(), and integrate().

Referenced by initialize().

```
8.1.5.5 emissivity
double jeod::ThermalFacetRider::emissivity {}
Fraction of sigma-T<sup>^</sup>4 (potential for emissive radiation) that is actually emitted.
trick_units(-)
Definition at line 148 of file thermal_facet_rider.hh.
Referenced by initialize().
8.1.5.6 facet
InteractionFacet* jeod::ThermalFacetRider::facet {}
Pointer back to facet that contains this thermal rider.
trick_units(-)
Definition at line 127 of file thermal facet rider.hh.
8.1.5.7 heat_capacity
double jeod::ThermalFacetRider::heat_capacity {}
Heat capacity of the facet.
trick_units(-)
Definition at line 115 of file thermal_facet_rider.hh.
Referenced by jeod::ThermalIntegrableObject::compute_temp_dot(), and integrate().
8.1.5.8 integrable_object
ThermalIntegrableObject jeod::ThermalFacetRider::integrable_object
The encapsulation of a first order integrator which can optionally be used to integrate the temperature.
trick_units(-)
Definition at line 154 of file thermal_facet_rider.hh.
```

8.1.5.9 next_temperature

```
double jeod::ThermalFacetRider::next_temperature {} [private]
```

The predicted value of temperature at the next time-step.

THIS VALUE IS USED ONLY BY THE THERMAL INTEGRATOR, AND SHOULD NOT BE SET EXTERNALLY. ← trick units(K)

Definition at line 169 of file thermal facet rider.hh.

Referenced by initialize(), and integrate().

8.1.5.10 power_absorb

```
double jeod::ThermalFacetRider::power_absorb {}
```

Rate at which energy is absorbed from the environment, vehicle, and surface.

trick_units(-)

Definition at line 102 of file thermal facet rider.hh.

Referenced by accumulate_thermal_sources(), jeod::ThermalIntegrableObject::compute_temp_dot(), jeod::

ThermalIntegrableObject::integrate(), and integrate().

8.1.5.11 power_emit

```
double jeod::ThermalFacetRider::power_emit {}
```

Rate at which energy is thermally radiated from the facet.

trick units(-)

Definition at line 107 of file thermal_facet_rider.hh.

Referenced by accumulate_thermal_sources(), jeod::ThermalIntegrableObject::compute_temp_dot(), and integrate().

8.1.5.12 rad_constant

```
double jeod::ThermalFacetRider::rad_constant {}
```

Combination of variables that are held constant for any given facet.

trick_units(-)

Definition at line 122 of file thermal_facet_rider.hh.

Referenced by jeod::ThermalIntegrableObject::compute_temp_dot(), initialize(), jeod::ThermalIntegrableObject::integrate(), and integrate().

8.1.5.13 stefan_boltzmann

```
const double jeod::ThermalFacetRider::stefan_boltzmann = 5.6704004E-08 [static], [protected]
```

Stefan-Boltzmann constant.

```
trick_io(*o) trick_units(-)
```

Definition at line 161 of file thermal_facet_rider.hh.

Referenced by initialize().

8.1.5.14 thermal_power_dump

```
double jeod::ThermalFacetRider::thermal_power_dump {}
```

Rate at which thermal energy is transferred to the facet from within the vehicle.

trick_units(-)

Definition at line 140 of file thermal_facet_rider.hh.

Referenced by accumulate thermal sources().

The documentation for this class was generated from the following files:


- thermal_facet_rider.hh
- thermal_facet_rider.cc

8.2 jeod::ThermalIntegrableObject Class Reference

Encapsulates a thermal integrator for a facet.

```
#include <thermal_integrable_object.hh>
```

Inheritance diagram for jeod::ThermalIntegrableObject:



Public Member Functions

• ThermalIntegrableObject ()

ThermalIntegrableObject default constructor.

∼ThermalIntegrableObject () override

ThermalIntegrableObject destructor.

- ThermalIntegrableObject & operator= (const ThermalIntegrableObject &)=delete
- ThermalIntegrableObject (const ThermalIntegrableObject &)=delete
- void initialize (double temperature, ThermalFacetRider &associated_rider)

Initialize temperature and cache a pointer to the ThermalFacetRider.

 void create_integrators (const er7_utils::IntegratorConstructor &generator, er7_utils::IntegrationControls &controls, const er7_utils::TimeInterface &time_if) override

Create the first order integrator for this IntegrableObject.

· void destroy_integrators () override

Destroy integrators for this IntegrableObject.

• void reset_integrators () override

Reset the integrator.

• er7_utils::IntegratorResult integrate (double dyn_dt, unsigned int target_stage) override

Integrate the thermal state.

void compute_temp_dot ()

Compute emitted power and the time derivative of temperature.

• double get_temp ()

Get the temperature.

double get_temp_dot ()

Get the temperature time derivative.

Data Fields

· bool active {}

If true, this IntegrableObject will integrate temperature.

Private Attributes

• RestartableScalarFirstOrderODEIntegrator integrator

Integrates temperature on one facet.

ThermalFacetRider * rider {}

Cached pointer to the associated ThermalFacetRider.

double temp {}

Temperature of the facet.

double temp_dot {}

Time derivative of temperature.

double t_pow4 {}

Fourth power of current temperature.

Friends

- class InputProcessor
- void init_attrjeod__ThermalIntegrableObject ()

8.2.1 Detailed Description

Encapsulates a thermal integrator for a facet.

Definition at line 87 of file thermal integrable object.hh.

8.2.2 Constructor & Destructor Documentation

```
8.2.2.1 ThermalIntegrableObject() [1/2]
```

```
jeod::ThermalIntegrableObject::ThermalIntegrableObject ( )
```

ThermalIntegrableObject default constructor.

Definition at line 47 of file thermal_integrable_object.cc.

References integrator.

8.2.2.2 \sim ThermalIntegrableObject()

```
jeod::ThermalIntegrableObject::~ThermalIntegrableObject ( ) [override]
```

 $Thermal Integrable Object\ destructor.$

Definition at line 56 of file thermal_integrable_object.cc.

References destroy_integrators(), and integrator.

8.2.2.3 ThermalIntegrableObject() [2/2]

8.2.3 Member Function Documentation

8.2.3.1 compute_temp_dot()

```
void jeod::ThermalIntegrableObject::compute_temp_dot ( )
```

Compute emitted power and the time derivative of temperature.

Definition at line 142 of file thermal integrable object.cc.

References jeod::ThermalFacetRider::heat_capacity, jeod::ThermalFacetRider::power_absorb, jeod::Thermal ← FacetRider::power_emit, jeod::ThermalFacetRider::rad_constant, rider, t_pow4, and temp_dot.

8.2.3.2 create_integrators()

Create the first order integrator for this IntegrableObject.

Parameters

generator	Integrator constructor that creates the integrator.
controls	Integration controls that mediates the integrations.
time_if	Unused.

Definition at line 68 of file thermal_integrable_object.cc.

References integrator.

8.2.3.3 destroy_integrators()

```
void jeod::ThermalIntegrableObject::destroy_integrators ( ) [override]
```

Destroy integrators for this IntegrableObject.

Definition at line 78 of file thermal_integrable_object.cc.

Referenced by \sim ThermalIntegrableObject().

8.2.3.4 get_temp()

```
double jeod::ThermalIntegrableObject::get_temp ( ) [inline]
```

Get the temperature.

Returns

Facet temperature.

Definition at line 121 of file thermal_integrable_object.hh.

8.2.3.5 get_temp_dot()

```
double jeod::ThermalIntegrableObject::get_temp_dot ( ) [inline]
```

Get the temperature time derivative.

Returns

Facet temperature time derivative.

Definition at line 130 of file thermal_integrable_object.hh.

8.2.3.6 initialize()

Initialize temperature and cache a pointer to the ThermalFacetRider.

Parameters

temperature	– initial temperature
associated_rider	- the associated ThermalFacetRider

Definition at line 131 of file thermal_integrable_object.cc.

References rider, t_pow4, and temp.

Referenced by jeod::ThermalFacetRider::initialize().

8.2.3.7 integrate()

```
er7_utils::IntegratorResult jeod::ThermalIntegrableObject::integrate ( \label{eq:double_dyn_dt} \mbox{double } dyn\_dt, \\ \mbox{unsigned int } target\_stage \mbox{)} \mbox{ [override]}
```

Integrate the thermal state.

Parameters

in	dyn_dt	Dynamic time step, in dynamic time seconds.
in	target_stage	The stage of the integration process that the integrator should try to attain.

Returns

The status (time advance, pass/fail status) of the integration.

Definition at line 98 of file thermal_integrable_object.cc.

References integrator, jeod::ThermalMessages::invalid_integration_operation, jeod::ThermalFacetRider::power_ absorb, jeod::ThermalFacetRider::rad_constant, rider, t_pow4, temp, and temp_dot.

8.2.3.8 operator=()

8.2.3.9 reset_integrators()

```
void jeod::ThermalIntegrableObject::reset_integrators ( ) [override]
```

Reset the integrator.

Definition at line 86 of file thermal_integrable_object.cc.

References integrator.

8.2.4 Friends And Related Function Documentation

8.2.4.1 init_attrjeod__ThermalIntegrableObject

```
void init_attrjeod__ThermalIntegrableObject ( ) [friend]
```

8.2.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 89 of file thermal_integrable_object.hh.

8.2.5 Field Documentation

8.2.5.1 active

```
bool jeod::ThermalIntegrableObject::active {}
```

If true, this IntegrableObject will integrate temperature.

trick_units(-)

Definition at line 140 of file thermal_integrable_object.hh.

8.2.5.2 integrator

```
RestartableScalarFirstOrderODEIntegrator jeod::ThermalIntegrableObject::integrator [private]
```

Integrates temperature on one facet.

trick_units(-)

Definition at line 147 of file thermal_integrable_object.hh.

Referenced by create_integrators(), integrate(), reset_integrators(), ThermalIntegrableObject(), and \sim Thermal \leftarrow IntegrableObject().

8.2.5.3 rider

```
ThermalFacetRider* jeod::ThermalIntegrableObject::rider {} [private]
```

Cached pointer to the associated ThermalFacetRider.

trick units(-)

Definition at line 152 of file thermal_integrable_object.hh.

Referenced by compute_temp_dot(), initialize(), and integrate().

8.2.5.4 t_pow4

```
double jeod::ThermalIntegrableObject::t_pow4 {} [private]
```

Fourth power of current temperature.

```
trick_units(K*K*K*K)
```

Definition at line 167 of file thermal_integrable_object.hh.

Referenced by compute_temp_dot(), initialize(), and integrate().

8.2.5.5 temp

```
double jeod::ThermalIntegrableObject::temp {} [private]
```

Temperature of the facet.

trick_units(K)

Definition at line 157 of file thermal_integrable_object.hh.

Referenced by initialize(), and integrate().

8.2.5.6 temp_dot

```
double jeod::ThermalIntegrableObject::temp_dot {} [private]
```

Time derivative of temperature.

trick_units(K/s)

Definition at line 162 of file thermal_integrable_object.hh.

Referenced by compute_temp_dot(), and integrate().

The documentation for this class was generated from the following files:

- thermal_integrable_object.hh
- thermal_integrable_object.cc

8.3 jeod::ThermalMessages Class Reference

Specifying the message IDs used in the model.

```
#include <thermal_messages.hh>
```

Public Member Functions

- ThermalMessages ()=delete
- ThermalMessages (const ThermalMessages &)=delete
- ThermalMessages & operator= (const ThermalMessages &)=delete

Static Public Attributes

- static const char * incomplete_setup_error = "utils/thermal_rider/" "incomplete_setup_error"

 Generic error; the model was not set up correctly.
- static const char * invalid_integration_operation = "utils/thermal_rider/" "invalid_integration_operation"

 The integration is invalid, usually because the integration step is too large.

Friends

- class InputProcessor
- void init_attrjeod__ThermalMessages ()

8.3.1 Detailed Description

Specifying the message IDs used in the model.

Definition at line 79 of file thermal_messages.hh.

8.3.2 Constructor & Destructor Documentation

```
8.3.2.1 ThermalMessages() [1/2]
```

```
jeod::ThermalMessages::ThermalMessages ( ) [delete]
```

8.3.2.2 ThermalMessages() [2/2]

8.3.3 Member Function Documentation

8.3.3.1 operator=()

8.3.4 Friends And Related Function Documentation

8.3.4.1 init_attrjeod__ThermalMessages

```
void init_attrjeod__ThermalMessages ( ) [friend]
```

8.3.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 81 of file thermal_messages.hh.

8.3.5 Field Documentation

8.3.5.1 incomplete_setup_error

```
const char * jeod::ThermalMessages::incomplete_setup_error = "utils/thermal_rider/" "incomplete←
_setup_error" [static]
```

Generic error; the model was not set up correctly.

trick_units(-)

Definition at line 87 of file thermal_messages.hh.

Referenced by jeod::ThermalFacetRider::initialize().

8.3.5.2 invalid_integration_operation

```
const char * jeod::ThermalMessages::invalid_integration_operation = "utils/thermal_rider/"
"invalid_integration_operation" [static]
```

The integration is invalid, usually because the integration step is too large.

trick_units(-)

Definition at line 93 of file thermal_messages.hh.

Referenced by jeod::ThermalIntegrableObject::integrate(), and jeod::ThermalFacetRider::integrate().

The documentation for this class was generated from the following files:

- · thermal_messages.hh
- thermal_messages.cc

8.4 jeod::ThermalModelRider Class Reference

Defining the thermal functionality.

```
#include <thermal_model_rider.hh>
```

Public Member Functions

- ThermalModelRider ()=default
- virtual ∼ThermalModelRider ()=default
- ThermalModelRider & operator= (const ThermalModelRider &)=delete
- ThermalModelRider (const ThermalModelRider &)=delete
- void update (InteractionSurface *surface_ptr)

update the thermal aspects of all facets

Data Fields

bool active {}

Flag to allow thermal variation of facets.

bool include_internal_thermal_effects {}

Flag to include facet-to-facet conduction, and vehicle-to-facet thermal sources and sinks.

Friends

- · class InputProcessor
- void init_attrjeod__ThermalModelRider ()

8.4.1 Detailed Description

Defining the thermal functionality.

Definition at line 82 of file thermal_model_rider.hh.

8.4.2 Constructor & Destructor Documentation

8.4.3 Member Function Documentation

8.4.3.1 operator=()

8.4.3.2 update()

update the thermal aspects of all facets

Parameters

```
in surface_ptr pointer the surface.
```

Definition at line 52 of file thermal_model_rider.cc.

References active, jeod::ThermalFacetRider::cycle_time, and include_internal_thermal_effects.

8.4.4 Friends And Related Function Documentation

8.4.4.1 init_attrjeod__ThermalModelRider

```
void init_attrjeod__ThermalModelRider ( ) [friend]
```

8.4.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 84 of file thermal_model_rider.hh.

8.4.5 Field Documentation

8.4.5.1 active

```
bool jeod::ThermalModelRider::active {}
```

Flag to allow thermal variation of facets.

```
trick_units(-)
```

Definition at line 88 of file thermal_model_rider.hh.

Referenced by update().

8.4.5.2 include_internal_thermal_effects

```
bool jeod::ThermalModelRider::include_internal_thermal_effects {}
```

Flag to include facet-to-facet conduction, and vehicle-to-facet thermal sources and sinks.

trick_units(-)

Definition at line 94 of file thermal model rider.hh.

Referenced by update().

The documentation for this class was generated from the following files:

- thermal_model_rider.hh
- thermal_model_rider.cc

8.5 jeod::ThermalParams Class Reference

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

```
#include <thermal_params.hh>
```

Public Member Functions

- ThermalParams ()=default
- virtual ∼ThermalParams ()=default
- ThermalParams & operator= (const ThermalParams &)=delete
- ThermalParams (const ThermalParams &)=delete

Data Fields

· double emissivity {}

Fraction of sigma- T^{\wedge} 4 (potential for emissive thermal) that is actually emitted.

double heat_capacity_per_area {1.0E+20}

Heat Capacity per unit area of surface.

double thermal_power_dump {}

Rate at which thermal energy is dumped (positive) / extracted (negative) into a facet from within the vehicle.

Friends

- · class InputProcessor
- void init_attrjeod__ThermalParams ()

8.5.1 Detailed Description

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

Definition at line 80 of file thermal_params.hh.

8.5.2 Constructor & Destructor Documentation

8.5.2.1 ThermalParams() [1/2]

```
jeod::ThermalParams::ThermalParams ( ) [default]
```

8.5.2.2 \sim ThermalParams()

```
virtual jeod::ThermalParams::~ThermalParams ( ) [virtual], [default]
```

8.5.2.3 ThermalParams() [2/2]

8.5.3 Member Function Documentation

8.5.3.1 operator=()

8.5.4 Friends And Related Function Documentation

8.5.4.1 init_attrjeod__ThermalParams

```
void init_attrjeod__ThermalParams ( ) [friend]
```

8.5.4.2 InputProcessor

```
friend class InputProcessor [friend]
```

Definition at line 82 of file thermal_params.hh.

8.5.5 Field Documentation

8.5.5.1 emissivity

```
double jeod::ThermalParams::emissivity {}
```

Fraction of sigma-T⁴ (potential for emissive thermal) that is actually emitted.

```
trick_units(-)
```

Definition at line 87 of file thermal_params.hh.

8.5.5.2 heat_capacity_per_area

```
double jeod::ThermalParams::heat_capacity_per_area {1.0E+20}
```

Heat Capacity per unit area of surface.

```
trick_units(-)
```

Definition at line 92 of file thermal_params.hh.

8.5.5.3 thermal_power_dump

```
double jeod::ThermalParams::thermal_power_dump {}
```

Rate at which thermal energy is dumped (positive) / extracted (negative) into a facet from within the vehicle.

Used for radiators and the like.trick_units(-)

Definition at line 99 of file thermal_params.hh.

The documentation for this class was generated from the following file:

• thermal_params.hh

Chapter 9

File Documentation

9.1 class_declarations.hh File Reference

Forward declaration of classes defined in Thermal_rider model.

Namespaces

• jeod

Namespace jeod.

9.1.1 Detailed Description

Forward declaration of classes defined in Thermal_rider model.

9.2 thermal_facet_rider.cc File Reference

ThermalFacetRider interaction model.

```
#include <cmath>
#include <cstddef>
#include "utils/message/include/message_handler.hh"
#include "../include/thermal_facet_rider.hh"
#include "../include/thermal_messages.hh"
```

Namespaces

• jeod

Namespace jeod.

42 File Documentation

Macros

#define pow4(x) pow4_temp = (x) * (x), pow4_temp *= pow4_temp

9.2.1 Detailed Description

ThermalFacetRider interaction model.

9.2.2 Macro Definition Documentation

9.2.2.1 pow4

```
#define pow4(  x \text{ ) pow4\_temp = (x) * (x), pow4\_temp *= pow4\_temp}
```

Referenced by jeod::ThermalFacetRider::integrate().

9.3 thermal_facet_rider.hh File Reference

Defining the thermal characteristics of surface facets.

```
#include "utils/sim_interface/include/jeod_class.hh"
#include "thermal_integrable_object.hh"
```

Data Structures

· class jeod::ThermalFacetRider

Defining the thermal characteristics of surface facets.

Namespaces

• jeod

Namespace jeod.

9.3.1 Detailed Description

Defining the thermal characteristics of surface facets.

9.4 thermal_integrable_object.cc File Reference

Encapsulates an integrator for a single facet.

```
#include <cmath>
#include "../include/thermal_facet_rider.hh"
#include "../include/thermal_integrable_object.hh"
#include "../include/thermal_messages.hh"
```

Namespaces

jeod

Namespace jeod.

9.4.1 Detailed Description

Encapsulates an integrator for a single facet.

9.5 thermal_integrable_object.hh File Reference

Define an IntegrableObject class adapted to thermal integration.

```
#include "er7_utils/integration/core/include/integrable_object.hh"
#include "er7_utils/integration/core/include/integrator_result.hh"
#include "utils/integration/include/restartable_state_integrator.hh"
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

• class jeod::ThermalIntegrableObject

Encapsulates a thermal integrator for a facet.

Namespaces

· jeod

Namespace jeod.

9.5.1 Detailed Description

Define an IntegrableObject class adapted to thermal integration.

44 File Documentation

9.6 thermal_messages.cc File Reference

Implement the class ThermalMessages.

```
#include "../include/thermal_messages.hh"
```

Namespaces

• jeod

Namespace jeod.

Macros

• #define PATH "utils/thermal_rider/"

9.6.1 Detailed Description

Implement the class ThermalMessages.

9.7 thermal_messages.hh File Reference

Define the class ThermalMessages, the class that specifies the message IDs used in the model.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

• class jeod::ThermalMessages

Specifying the message IDs used in the model.

Namespaces

· jeod

Namespace jeod.

9.7.1 Detailed Description

Define the class ThermalMessages, the class that specifies the message IDs used in the model.

9.8 thermal_model_rider.cc File Reference

ThermalModelRider interaction model.

```
#include <cmath>
#include "../include/thermal_facet_rider.hh"
#include "../include/thermal_model_rider.hh"
#include "utils/surface_model/include/interaction_surface.hh"
```

Namespaces

jeod

Namespace jeod.

9.8.1 Detailed Description

ThermalModelRider interaction model.

9.9 thermal_model_rider.hh File Reference

Defining the thermal functionality.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

Data Structures

class jeod::ThermalModelRider
 Defining the thermal functionality.

Namespaces

• jeod

Namespace jeod.

9.9.1 Detailed Description

Defining the thermal functionality.

9.10 thermal_params.hh File Reference

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

```
#include "utils/sim_interface/include/jeod_class.hh"
```

46 File Documentation

Data Structures

• class jeod::ThermalParams

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

Namespaces

• jeod

Namespace jeod.

9.10.1 Detailed Description

A virtual base class for thermal facet parameters, used to add to the parameter lists for specific-model facets in their respective InteractionSurfaceFactorys.

Index

\sim ThermalFacetRider	jeod::ThermalMessages, 33
jeod::ThermalFacetRider, 18	init_attrjeodThermalFacetRider
~ThermalIntegrableObject	jeod::ThermalFacetRider, 20
jeod::ThermalIntegrableObject, 26	init_attrjeodThermalIntegrableObject
\sim ThermalModelRider	jeod::ThermalIntegrableObject, 29
jeod::ThermalModelRider, 35	init_attrjeodThermalMessages
~ThermalParams	jeod::ThermalMessages, 33
jeod::ThermalParams, 37	init_attrjeodThermalModelRider
•	jeod::ThermalModelRider, 36
accumulate_thermal_sources	init_attrjeodThermalParams
jeod::ThermalFacetRider, 19	jeod::ThermalParams, 38
active	initialize
jeod::ThermalFacetRider, 20	jeod::ThermalFacetRider, 19
jeod::ThermalIntegrableObject, 30	jeod::ThermalIntegrableObject, 28
jeod::ThermalModelRider, 36	InputProcessor
•	jeod::ThermalFacetRider, 20
class_declarations.hh, 41	jeod::ThermalIntegrableObject, 29
compute_temp_dot	jeod::ThermalMessages, 33
jeod::ThermalIntegrableObject, 26	jeod::ThermalModelRider, 36
create integrators	jeod::ThermalParams, 38
jeod::ThermalIntegrableObject, 27	integrable_object
cycle_time	jeod::ThermalFacetRider, 22
jeod::ThermalFacetRider, 21	
,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,,	integrate jeod::ThermalFacetRider, 19
d_temperature	·
jeod::ThermalFacetRider, 21	jeod::ThermalIntegrableObject, 28
destroy_integrators	integrator
jeod::ThermalIntegrableObject, 27	jeod::ThermalIntegrableObject, 30
dynamic_temperature	Interactions, 12
jeod::ThermalFacetRider, 21	invalid_integration_operation
•	jeod::ThermalMessages, 33
emissivity	jeod, 15
jeod::ThermalFacetRider, 21	jeod; 13 jeod::ThermalFacetRider, 17
jeod::ThermalParams, 38	~ThermalFacetRider, 18
	accumulate_thermal_sources, 19
facet	active, 20
jeod::ThermalFacetRider, 22	cycle_time, 21
get_temp	d_temperature, 21 dynamic_temperature, 21
jeod::ThermalIntegrableObject, 27	
get_temp_dot	emissivity, 21
jeod::ThermalIntegrableObject, 28	facet, 22
	heat_capacity, 22
heat_capacity	init_attrjeodThermalFacetRider, 2
jeod::ThermalFacetRider, 22	initialize, 19
heat_capacity_per_area	InputProcessor, 20
jeod::ThermalParams, 39	integrable_object, 22
	integrate, 19
include_internal_thermal_effects	next_temperature, 22
jeod::ThermalModelRider, 36	operator=, 20
incomplete setup error	power absorb, 23

48 INDEX

power_emit, 23	jeod::ThermalMessages, 32
rad_constant, 23	jeod::ThermalModelRider, 35
stefan_boltzmann, 23	jeod::ThermalParams, 38
thermal_power_dump, 24	
ThermalFacetRider, 18, 19	PATH
jeod::ThermalIntegrableObject, 24	ThermalRider, 13
~ThermalIntegrableObject, 26	pow4
active, 30	thermal_facet_rider.cc, 42
compute_temp_dot, 26	power absorb
create_integrators, 27	jeod::ThermalFacetRider, 23
destroy integrators, 27	power_emit
get_temp, 27	jeod::ThermalFacetRider, 23
get_temp_dot, 28	•
init_attrjeodThermalIntegrableObject, 29	rad_constant
	jeod::ThermalFacetRider, 23
initialize, 28	reset_integrators
InputProcessor, 29	jeod::ThermalIntegrableObject, 29
integrate, 28	rider
integrator, 30	jeod::ThermalIntegrableObject, 30
operator=, 29	,
reset_integrators, 29	stefan boltzmann
rider, 30	jeod::ThermalFacetRider, 23
t_pow4, 30	•
temp, 31	t_pow4
temp_dot, 31	jeod::ThermalIntegrableObject, 30
ThermalIntegrableObject, 26	temp
jeod::ThermalMessages, 31	jeod::ThermalIntegrableObject, 31
incomplete_setup_error, 33	temp_dot
init_attrjeodThermalMessages, 33	jeod::ThermalIntegrableObject, 31
InputProcessor, 33	thermal_facet_rider.cc, 41
invalid_integration_operation, 33	pow4, 42
operator=, 32	thermal_facet_rider.hh, 42
ThermalMessages, 32	thermal_integrable_object.cc, 43
jeod::ThermalModelRider, 34	thermal_integrable_object.hh, 43
∼ThermalModelRider, 35	thermal_messages.cc, 44
active, 36	thermal_messages.hh, 44
include_internal_thermal_effects, 36	thermal_model_rider.cc, 45
init_attrjeodThermalModelRider, 36	thermal_model_rider.hh, 45
InputProcessor, 36	thermal_params.hh, 45
operator=, 35	thermal power dump
ThermalModelRider, 35	jeod::ThermalFacetRider, 24
update, 35	•
jeod::ThermalParams, 37	jeod::ThermalParams, 39
~ThermalParams, 37	ThermalFacetRider
emissivity, 38	jeod::ThermalFacetRider, 18, 19
heat_capacity_per_area, 39	ThermalIntegrableObject
init_attrjeodThermalParams, 38	jeod::ThermalIntegrableObject, 26
InputProcessor, 38	ThermalMessages
operator=, 38	jeod::ThermalMessages, 32
thermal_power_dump, 39	ThermalModelRider
ThermalParams, 37, 38	jeod::ThermalModelRider, 35
memarams, 37, 30	ThermalParams
Models, 11	jeod::ThermalParams, 37, 38
Widdels, 11	ThermalRider, 13
next_temperature	PATH, 13
jeod::ThermalFacetRider, 22	
jood morman doon noon, LL	update
operator=	jeod::ThermalModelRider, 35
jeod::ThermalFacetRider, 20	
ieod::ThermalIntegrableObject, 29	