

Easy Vehicle Steering - Documentation

Version: 1.1

Compatibility: Unity 2019.4 LTS and above

Table of Contents

1. Introduction
2. Core Concept: The InputHandler
3. Steering Control Methods
 - 3.1. Steering Buttons
 - 3.2. Steering Drag Slider
 - 3.3. Steering Wheel
4. Direct Mode Access (NEW FEATURE)
5. Integration with Your Vehicle
6. Example & Testing (TEST.cs)
7. Troubleshooting & Tips

1. Introduction

The Easy Vehicle Steering package provides a robust and flexible system for implementing various mobile-friendly and editor-friendly vehicle steering UI controls. It abstracts the input source, allowing your vehicle's steering logic to remain clean and consistent, whether the player is using keyboard keys, on-screen buttons, a drag slider, or a virtual steering wheel.

2. Core Concept: The InputHandler

The InputHandler class is the heart of this package. It acts as a single point of input for your vehicle's steering, seamlessly switching between real keyboard input and simulated input from the UI controls.

Key Features:

- Platform Awareness
- Input Simulation
- Automatic Cleanup

Usage Example:

```
float steerInput = InputHandler.Horizontal;
```

3. Steering Control Methods

This package includes three ready-to-use UI steering methods.

3.1. Steering Buttons

Provides simple "Left" and "Right" buttons for digital steering input.

3.2. Steering Drag Slider

Provides analog-style steering by dragging a handle within a defined area.

3.3. Steering Wheel

Provides a virtual steering wheel that players can rotate for input.

4. Direct Mode Access (NEW FEATURE)

You can now directly access the `steerValue` from any steering component.

Useful for combining multiple control types or implementing custom input logic.

Examples:

- `DirectSteeringController`: Access `steerValue` directly from a component.
- `MultiSteeringController`: Combine multiple control types with priority.
- `EventSteeringController`: Read `steerValue` dynamically for debugging or custom logic.

5. Integration with Your Vehicle

Choose your control method:

- `InputHandler.Horizontal` (universal and automatic)
- Direct Mode (manual steering control references)

Example (`AdvancedCarController`):

- Uses `SteeringWheel.steerValue` for direct physics-based steering.

6. Example & Testing (TEST.cs)

Use the included TEST script to visualize steering input with a UI slider.

7. Troubleshooting & Tips

- No Input in Build: Check UI setup and `InputHandler` usage.
- Input Feels Laggy: Increase Return Speed values.
- Buttons Not Working: Ensure `EventTrigger` and Canvas setup.
- Direct Mode Not Working: Verify component references.
- Use TEST script for debugging.

Summary of Input Options:

- `InputHandler.Horizontal` → Universal input (recommended)
- `steeringWheel.steerValue` → Direct access
- `steeringDrag.steerValue` → Direct access
- `steeringButtons.steerValue` → Direct access

For support or feedback, contact us via the Unity Asset Store.

Happy Driving!