# Contents

1	$\operatorname{Lec}$	Lecture Notes on x86-64 Assembly Basics		
	1.1	Introduction to x86-64 Assembly		
		1.1.1	Registers Overview	
		1.1.2	Register Naming Conventions	
		1.1.3	Memory Addressing Modes	
		1.1.4	Instruction Set Overview	
		1.1.5	Examples and Explanation	
	1.2	Practi	cal Application and Memory Addressing	
		1.2.1	Closing Tips for Assembly Programming	
2	Cor	ncludin	ng Remarks	

## 1 Lecture Notes on x86-64 Assembly Basics

Welcome to today's lecture on x86-64 assembly basics. We'll cover various fundamental aspects, including register usage, memory addressing, and instruction sets, focusing specifically on move and LEAQ instructions. This lecture is essential for understanding low-level programming and is fundamental for courses like operating systems or computer architecture.

## 1.1 Introduction to x86-64 Assembly

x86-64 is an extension of the x86 instruction set that supports 64-bit computing, offering enhanced performance through a broader set of registers and more extensive memory addressing capabilities.

#### 1.1.1 Registers Overview

- Registers are small, high-speed storage locations directly within the CPU used to store temporary data.
- In x86-64, there are 16 general-purpose registers named RAX, RBX, RCX, RDX, RSI, RDI, RBP, RSP, and R8 to R15.
- RAX, RBX, RCX, and RDX are the primary general-purpose registers with historical significance and specific use cases.
- **RSI** and **RDI** are typically used for source and destination indices in string operations.
- **RBP** and **RSP** are used for base and stack pointers, crucial for function call management.
- Registers can be accessed entirely (64-bit), or in parts (32-bit as EAX or 8-bit AL), to support backward compatibility with older 32-bit and 8-bit software.

#### 1.1.2 Register Naming Conventions

Register naming conventions follow a pattern where "R" indicates a 64-bit register (e.g., RAX), "E" indicates a 32-bit register (e.g., EAX), and no prefix with "H" or "L" suffixes indicates high or low 8-bit parts of the register (e.g., AH or AL).

### 1.1.3 Memory Addressing Modes

Memory addressing in x86-64 allows for various modes to access data:

1. **Immediate Addressing:** Uses a constant value within the instruction. e.g., mov \$5, %rax

- 2. **Register Addressing:** Uses the content of a register as the operand. e.g., mov %rax, %rbx
- 3. **Memory Addressing:** Accesses data in memory through complex addressing modes involving registers and constants.

#### 1.1.4 Instruction Set Overview

- The **x86-64 instruction set** encompasses a wide range of operations, including arithmetic, logic, control flow, and data movement.
- Move Instruction (mov/movq): Transfers data between registers, memory and immediate values. It's akin to copying rather than moving in high-level programming.
- Load Effective Address (LEAQ): Computes the effective address of the operand and stores it in a register without accessing the memory. This instruction can perform arithmetic operations like addition or multiplication by powers of two without executing arithmetic instructions.

#### 1.1.5 Examples and Explanation

#### Move Instruction

- MoveQ is used to move 64-bit data and has the syntax move source, destination.
- Immediate to Register: movq \$5, %rax moves the constant 5 to RAX.
- Register to Memory: movq %rax, (%rbx) moves RAX's value to the memory address contained in RBX.

### LEA Instruction

- LEAQ is particularly useful for calculating addresses or simple arithmetic without accessing memory.
- Example: leaq (%rdi, %rsi, 4), %rax computes the address that is the sum of RDI's content and RSI's content times four, storing the result in RAX.

#### 1.2 Practical Application and Memory Addressing

- Memory Operations: In x86-64, operations directly involving memory are powerful but require careful handling of addressing modes.
- Addressing Modes: The combination of base registers, index registers, scaling factors, and displacements offers flexibility in generating addresses dynamically during program execution.

• Use of LEAQ: Beyond calculating addresses, LEAQ can be used for several arithmetic operations like multiplying a register value by constants (e.g., leaq 0(,%rdi,4), %rax multiplies RDI by four).

#### 1.2.1 Closing Tips for Assembly Programming

- Understand the Register Usage: Knowing which registers to use for specific tasks can optimize your assembly code.
- Master the Addressing Modes: Complex memory operations often hinge on effectively using the various addressing modes.
- Limit Direct Memory Access: If possible, use registers for intermediate calculations to reduce costly memory accesses.

# 2 Concluding Remarks

Today's lecture introduced you to the basics of x86-64 assembly, focusing on registers, addressing modes, and key instructions like move and LEA. Understanding these concepts is vital for efficient low-level programming and will serve as a foundation for exploring more complex assembly programming techniques.