

Harmonic Patterns SwingCore

Nestor Mendez

August 2026

Contents

1	Installation	2
1.1	Prerequisites	2
1.2	Option A — Install from the MetaQuotes Market (recommended)	2
1.3	Option B — Manual installation (.ex5 file)	2
1.4	How to apply the indicator to a chart	2
1.5	Verifying a correct installation	3
2	Usage Manual (Input Parameters)	4
2.1	General Settings	4
2.2	Harmonics Settings	4
2.3	Alerts Settings	5
2.4	ZigZag Settings	5
3	Usage Tips	6
4	Disclaimer	7

1 Installation

This indicator runs on the **MetaTrader 5** platform. Installation takes a few minutes and requires no technical knowledge.

1.1 Prerequisites

- MetaTrader 5 installed and running.
- The standard **Heiken Ashi** indicator available in MetaTrader's examples folder (included by default in `Indicators\Examples\Heiken_Ashi`). The indicator uses it internally as a calculation base.

1.2 Option A — Install from the MetaQuotes Market (recommended)

1. Open MetaTrader 5.
2. Open the **Navigator** window with **Ctrl+N** (or via **View → Navigator**). Indicators and Expert Advisors are listed there.
3. In the **Market** section, search for “**Harmonic Patterns SwingCore**”.
4. Press **Buy** (Pro version) or **Download** (free Lite version).
5. The indicator installs automatically and appears in the Navigator under **Indicators → Market**.

1.3 Option B — Manual installation (.ex5 file)

1. Open MetaTrader 5.
2. Go to **File → Open Data Folder**.
3. Navigate to: `MQL5 → Indicators`.
4. Copy the indicator file (`.ex5`) into that folder.
5. Back in MetaTrader 5, right-click **Indicators** in the Navigator and select **Refresh**.
6. The indicator appears in the list, ready to use.

1.4 How to apply the indicator to a chart

1. Open the chart of the instrument you want to analyze (for example, XAUUSD or BTCUSD).
2. Select the desired timeframe (for example, M1).
3. Open the **Navigator** with **Ctrl+N** and locate **Harmonic Patterns SwingCore** under Indicators.
4. Drag it onto the chart, or double-click it.

5. The parameter window opens. Adjust the settings following Part 2 of this manual and press **OK**.

1.5 Verifying a correct installation

- The indicator begins scanning the chart. After a few seconds, the peak-and-valley zigzag appears, along with any detected harmonic patterns.
- When loading over extensive history, the process may take a moment. If the chart has little history loaded, scroll left so MetaTrader loads more bars.

2 Usage Manual (Input Parameters)

Each parameter of the configuration window is described below, grouped by section. The heading of each item matches the label shown in the indicator's property window.

2.1 General Settings

Timeframe (Detection timeframe) The timeframe on which detection runs. With `PERIOD_CURRENT`, the indicator uses the active chart's timeframe. Leave as is unless you want to force a specific timeframe.

Recommended: `PERIOD_CURRENT`

Clean Objects (Clear chart objects) When `true`, deletes all chart objects. This is a manual cleanup utility: enable it, let it clean, then set it back to `false`. Use it if the chart has accumulated objects from previous sessions.

Recommended: `false`

2.2 Harmonics Settings

Classic:true/Geometric:false (Detection method) Selects the detection method. With `true`, the classic (ratio-based) method is used; with `false`, the geometric (rule-based) method is used. Both detect the same six patterns with different criteria.

Recommended: `true`

Note on the Lite version: in the free version, the geometric method is disabled. Setting this parameter to `false` will display no patterns. The geometric method is available only in the Pro version.

Scan Harmonics (Enable pattern detection) Enables or disables pattern detection entirely. With `false`, the indicator shows only the structure zigzag, without marking patterns.

Recommended: `true`

Show percentages (Per-leg percentage labels) Displays on the chart the percentage of each leg of the most recent pattern (XA, AB, BC, CD, XD), expressed as a proportion of its reference leg. Useful for visually verifying the ratios.

Recommended: `true`

Show horizontal line (Horizontal line from D) Draws a horizontal line projected from point D (pattern completion) into the future. Serves as a visual reference of the price level where the pattern completed.

Recommended: `true`

Show Fibonacci targets (Fibonacci projection levels) Displays the Fibonacci projection levels of the most recent pattern, both in the pattern's direction (direct) and on the opposite side (inverse or mirror). Projected levels are: 38.2%, 50.0%, 61.8%, 100.0%, 161.8%, 261.8%, and 361.8%.

Recommended: `true`

Ratio tolerance (Ratio tolerance) Defines how much deviation is allowed in the ratios for a pattern to be considered valid. A lower value (for example, 0.05) makes detection stricter: fewer but more precise patterns. A higher value (for example, 0.20) is more permissive: more patterns, but less closely matched to the ideal proportion.

Default: 0.15

2.3 Alerts Settings

Enable alerts (Master alert switch) Master switch for the alert system. With **false**, no alert is issued even if the sub-settings are active.

Recommended: true

Visual pop-up (Visual pop-up alert) Shows a pop-up window in the terminal when a new pattern appears.

Recommended: true

Sound alert (Sound alert) Plays a sound when a new pattern appears. Requires the sound file to be available (see next parameter).

Recommended: your preference.

Audio file alert (Sound file name) Name of the sound file played with the audio alert. The file must be in MetaTrader's Sounds folder.

Default: alert.wav (included with the platform)

Alert repeats (Alert repeat count) Number of times the alert repeats when a new pattern appears. The alert sounds on the bar where the pattern appears and repeats on the following bars until this count is reached, then stops automatically.

Default: 5

2.4 ZigZag Settings

Windows Back (Scan window - bars back) Number of bars back the indicator analyzes to build the structure and search for patterns. A larger value shows more history and older patterns, at the cost of heavier computation. A smaller value focuses on recent data and is lighter.

Default: 21600

Ratio prominence (Minimum prominence) Controls how pronounced a price turn must be to count as a valid peak or valley. A higher value filters out small turns (fewer points, cleaner structure); a lower value is more sensitive (more points, more noise). This is one of the key parameters for tuning detection sensitivity.

Default: 2.0

3 Usage Tips

- **Start with the defaults.** They are calibrated for general use. Adjust `Ratio tolerance` and `Ratio prominence` only once you understand how they affect detection.
- **Structure comes first.** If the zigzag does not reflect the turns you consider relevant, adjust `Ratio prominence` before anything else: pattern quality depends on the quality of peak-and-valley detection.
- **More tolerance is not better.** Increasing `Ratio tolerance` produces more patterns, but less faithful to the ideal proportion. Fewer well-formed patterns are usually more useful than many approximate ones.
- **Convergence matters.** When several patterns coincide in the same price area, that area gains relevance as a possible support or resistance.

4 Disclaimer

This indicator is a technical-analysis tool provided for informational and demonstrative purposes only. **It does not constitute financial advice or any trading recommendation.**

Pattern detection is the result of a geometric calculation and does not represent a prediction of future market behavior. Past performance does not guarantee future results. Trading financial markets carries a high risk of loss.

You assume the entire risk of any decision you make based on this indicator.

Harmonic Patterns SwingCore

Version: 1.0

Last Updated: August 2026

Copyright © 2026, Nestor Mendez