WiFi settings for WINDOWS 7 (using free SecureW2)


(Many versions Windows 7 doesn't support network authentication method "Cisco:PEAP" and this manual is valid for those devices)

<u>Step 1:</u> Install <u>free SecureW2</u> (available in intranet software repository) in your Windows 7 device.

Step 2: Open Network and Sharing Center

Right-click mouse button on the wireless network icon in the taskbar (bottom right on the desktop). Select *Open Network and Sharing Center*:






You can also find your network connections:

by clicking the Start button \rightarrow clicking Control Panel \rightarrow clicking Network and Internet \rightarrow clicking Network and Sharing Center

Step 3: The following pop-up box should emerge and click on **"Set up a new connection or network"**:




Step 4: Select "Manually connect to a wireless network" and click on "Next"



Step 5: Do the setting as follows and click on "Next" (*Note:* Network name is case-sensitive.)



<u>Step 5:</u> After adding the wireless network **IITG_WIFI** successfully, click on the "**Change connection settings**". Pop-up window will appear.



<u>Step 6:</u> Select **Security tab** and Choose network authentication method as **"SecureW2: SecureW2 EAP-TTLS"**, then click on **"Settings"**



Step 7: Now "**SecureW2 Configuration**" window will popup. Click on "**Configure**".





Step 8: Deselect "Use alternate outer identity" and click on "Certificate" tab

Step 9: Deselect "**verify server certificate**" and click on "**Authentication**" tab



Step 10: Select Authentication Method: "PAP" and click on "User account" tab



Step 11: Select "**Prompt user for credential**" check box and click on "**OK**" And also click "**OK**" on previously open windows



Step 12: Now a pop-up will appear at network connection icon in the task bar asking for credentials

. Click on the popup



Step 13: Enter your IITG Webmail Username and Password, leave domain as blank and get connected to **IITG_WIFI**.



Note:

- Steps 1 to 11 are one time settings and Steps 12-13 need to perform every time you connect to IITG_WIFI
- After connecting to IITG_WIFI, <u>do the proxy settings</u> and then you are connected to internet
- Report any connection problem to netadmin@iitg.ernet.in