Any way to disable or hide Visual Studio Code's scrollbar/minimap?

Asked 2 years, 11 months ago Active 10 days ago Viewed 47k times



For the life of me I can't find any option, setting, or keyboard shortcut that disables or hides that annoying scrollbar. I just don't find it useful and it's distracting. Can't just edit the editor's CSS like Atom, either.

137

visual-studio-code vsco

vscode-settings



19



10 Answers



Remove Minimap

172

Add the following to your settings.json file



"editor.minimap.enabled": false



Note that, as pointed out in another answer, this process has now been simplified to:

View->Toggle Minimap

Remove the Overview Ruler

Add the following to your settings.json file

"editor.hideCursorInOverviewRuler": true

This will keep the scrollbar, but will result in it only appearing when the cursor is within the editor, as seen in the image below:



Completely remove scrollbars (requires restart)

If you would like to completely remove the scrollbars, add the following to your settings.json file (note the editor will say "Unknown configuration setting" - ignore this. It will still work):

```
"editor.scrollbar.horizontal": "hidden",
"editor.scrollbar.vertical": "hidden"
```

This will result in the scrollbars not being visible even when the cursor is in the editor, as seen in the image below:



edited Sep 18 '18 at 16:02

answered Jan 5 '17 at 9:28



badfilms 2,338 1

1 9

- 19 hmm. those "editor.scrollbar.*" entries give me "Unknown configuration setting" Lokua Mar 11 '17 at 20:19
- Alexandru Marculescu has the right answer if you're looking to disable the 'minimap', which is what I was looking for when I stumbled upon this question. :) Bryan Green Jul 25 '17 at 3:40 🖍
- 5 You need to restart vscode. It's an unoffical method to hid scroll bars that's why giving that error. here T K Sourabh Jan 5 '18 at 11:31 🖍

To make these scrollbars appear to hide, you can use RGBA colouring for scrollbarSlider attributes in your workbench.colorCustomizations settings. For example, setting all of the attributes to #000000 . — Florian Suess Feb 5 at 3:43 /

1 In my case I don't even have to restart. – JouleV Oct 13 at 14:02

Ctrl + Shift + P -> Open User Settings

163 "editor.minimap.enabled": false

answered Jun 13 '17 at 9:53



Alexandru Marculescu

4,690 6 27 42

Once you have the settings file opened. It's recommended to make this change under the User Settings section on the right window, that will overwrite the defaults settings. It's a better way to control your personal preferences in VS Code. - Ernesto Iser Sep 8 '17 at 18:45

Or even faster: Ctrl+, (comma) to open user-settings - Vadym Kyrylkov Feb 19 '18 at 18:13



Try this,

view->toggle minimap





neouyghur




This should be marked as answer. - Bivo Kasaju Sep 13 '18 at 14:08



So this is an unofficial method as instructed on accepted answer by @badfilms. You can read about it here

After adding, restart vscode:



This gives and "Unknown configuration settings", ignore it.

Then to remove the scrollbar seperator or ruler border, add this:

"editor.overviewRulerBorder": false

answered Jan 5 '18 at 11:35





tested Visual Studio version: VS Community 2017 Version 15.8.2



Tools --> Options



Search for "scroll"

click on "Text Editor" title from the results on the left side.

click "Use bar mode for vertical scroll bar" under "Behavior" section and then click "OK"

Here is a screenshot: Turn off Scroll Bar map mode

edited Sep 10 '18 at 12:53

answered Sep 10 '18 at 12:32



AntiqTech



View --> Show Minimap -click it to uncheck it-





answered Sep 7 at 14:29



Madeline McIntosh



Removing the scroll bar



These no longer work:



```
"editor.scrollbar.horizontal": "hidden",
"editor.scrollbar.vertical": "hidden"
```

However, this will set the size of the scroll bar to 0:

```
"editor.scrollbar.verticalScrollbarSize": 0,
```

The toolip says "Unknown Configuration Setting" but it works for me. (Visual Studio Code 1.39.2)

answered Oct 22 at 13:25





Default value of Scroll Beyond Last Column is 5 which does horizontal scrollbar visible and operate. Set the value to 0 removes horizontal scrollbar.

0

Settings options





once you go to the user setting it has default setting left had side as bellow and there is a pensile mark on where click and automatically appear true false then right had side custom setting change. Thats how I did it thanks Alexandru. think this may help you.



```
news-event.component.html
                                                                                    {} User Settings ×
                                                                                                         TS mock-news.ts
                                                                                                                              # tour-detail.component.css
                                                    TS news-event.component.ts
                                                                                                                 4 Settings matched
                      editor.minimap
                                                                                                                                         USER SETTINGS
                      DEFAULT SETTINGS
                                                                                                   Place your settings here to overwrite the Default Settings.
                                                                                                       "workbench.activityBar.visible": true,
                     "workbench.statusBar.visible": true,
                                                                                                       "git.confirmSync": false,
                        Controls if the minimap is shown
                                                                                                       "git.enableSmartCommit": true,
                       "edit .minimap.enabled": true,
                                                                                                       "editor.minimap.enabled": false
questions
                      // Controls whether the minimap slider is automatically
                      hidden. Possible values are 'always' and 'mouseover'
                      "editor.minimap.showSlider": "mouseover",
mponent.css
mponent.html
mponent.spec.ts
                      "editor.minimap.renderCharacters": true,
mponent.ts
                      // Limit the width of the minimap to render at most a certain
component.css
                      "editor.minimap.maxColumn": 120,
component.html
```

answered Oct 9 '17 at 7:52




Exactly what I needed, thanks! - Shaun Jun 28 '18 at 18:14



Goto View and deselect Minimap.







edited Nov 1 at 7:00

answered Oct 29 at 12:37

