Keyboard	planck/rev6
Layout	LAYOUT_ortho_4x12
Author	Hans Kruse
Date	7/22/2022 10:45:18 AM
Source	https://github.com/qmk/qmk_firmware/tree/master/keyboards/planck/rev6
Notes	Removed non Qwerty layouts. Added left/right mouse and browse layers. Added left/right numpad.

Layer 0

Q	W	E	R	T	Print Screen	TO(1)	Y	U	I	O	P
A	LCTL_T (KC_S)	LALT_T (KC_D)	LGUI_T (KC_F)	LSFT_T (KC_G)	Scroll Lock	Pause	RSFT_T (KC_H)	RGUI_T (KC_J)	RALT_T (KC_K)	RCTL_T (KC_L)	: ;
~	Z	X	C	V		Menu	B	N	M	? /	" '
LT 8, KC_AT	ALL_T (KC_ESC)	LT 3, KC_TAB	LT 5, KC_DEL	Space	Space	Enter	Enter	LT 4, KC_BSPC	LT 2, KC_COMM	> .	LT 7, KC_HASH

Layer 1

X	V	L	C	W	▽	TO(0)	K	H	G	F	Q
U	LCTL_T (KC_I)	LALT (KC_A)	LGUI_T (KC_E)	LSFT_T (KC_O)	▽	▽	RSFT_T (KC_S)	RGUI_T (KC_N)	RALT_T (KC_R)	RCTL_T (KC_T)	D
▽	: ;	" '	P	Z	▽	▽	B	M	J	▽	Y
▽	▽	▽	▽	▽	▽	▽	▽	▽	▽	▽	▽

Layer 2

!	(	)	%	~	^	&					
_	{	}	^	+ =	^	?	Right Shift	Right OS	Right Alt	Right Ctrl	
#	{ [	}]	&	|	$	%					
@	<	>	Tab	Delete	*	$		TO(6)		Caps Lock	

Layer 3

Lock. Caps Lock	Lock. Num Lock	Lock. Scroll Lock		Browser Search	Browser Stop	Browser Back	Mouse Left	Mouse Down	Mouse Up	Mouse Right	Browser Forward	
Left Shift	Menu	Browser Favorites	Mouse Accel 0	Mouse Accel 1	Mouse Accel 2	Browser Home	Mouse Wheel Left	Mouse Wheel Down	Mouse Wheel Up	Mouse Wheel Right	Browser Search	
Left Shift	Left Alt		Browser Favorites	Browser Refresh	Space	Enter	Mouse 1	Mouse 2	Mouse 3	Mouse 4	Mouse 5	

Layer 4

!	& 7	* 8	(9	*	/	|	Print Screen		Brightness Down	Brightness Up
-	$ 4	% 5	^ 6	+	^	?	Right Shift	Right OS	Right Alt	Right Ctrl
.	! 1	@ 2	# 3	,	%	$				
:	"	_	) 0	=	~	~	MO(6)		Caps Lock	

Layer 5

						Cut	Copy	Paste	Again	Undo
Caps Lock	Left Ctrl	Left Alt	Left OS	Left Shift		Left	Down	Up	Right	
Left Shift						Home	Page Down	Page Up	End	Right Shift

Layer 6

	Reset	Debug			BL -	BL +	RGB Mode T	RGB Mode P	RGB Mode B	RGB Mode R	RGB Mode SW
EEPROM Reset				BL Off	BL On	BL Toggle	RGB Mode SN	RGB Mode K	RGB Mode X	RGB Mode G
MU_ OFF	MU_ ON	RGB Mode -	RGB Mode +		Effect -	Effect +	RGB Toggle	Hue -	Sat -	Sat +	
MI_ OFF	MI_ ON	Brightness Down	Brightness Up					Bright -	Bright +	Sat +

Layer 7

My PC	Media Player	F7	F8	F9	Print Screen	Power	F17	F18	F19	F23	F24
Calc	LCTL_T (KC_MAIL)	LALT_T (KC_F4)	LGUI_T (KC_F6)	LSFT_T (KC_F6)	Scroll Lock	Sleep	RSFT_T (KC_F14)	RGUI_T (KC_F15)	RALT_T (KC_F16)	RCTL_T (KC_F21)	F22
	Menu (Legacy)	F1	F2	F3	Pause	Wake	F11	F12	F13	Help	
				F10		F20				

Layer 8

	Left Ctrl	Left Alt	Left OS	Left Shift		Previous	Vol -	Vol +	Next		
						Prev Track	Eject	Pause	Next Track		
						Media Stop	Play	Mute			