Navigation guide

Click through the menu; each view explains itself

Generated

2026-11-02 07:27:44 +01:00

Warning

GLOBAL banner (no -NavPath): it is on every view. Maintenance window Saturday 02:00-04:00 UTC.

Summary 3

24	14	8
VOLUMES	SNAPSHOTS	HOSTS

Home

What you are looking at

The banner above and the three KPI tiles under it are GLOBAL: declared with no path, so they stay on screen on every view. This note, and everything else below the tiles, is bound to the exact path Home.

Storage

Summary 2

58	6
USED (AVERAGE)	UNTAGGED

What you are looking at

Storage has its own content (this note) and, because of -NavAllLabel, a view called "All storage" next to Capacity, Tagging and Snapshots. Open it: it shows this note, the KPI strip, and everything under Storage at once.

Storage › Snapshots

What you are looking at

This view is declared after Capacity and Tagging but appears first in the Storage group: -NavOrder 1 orders this node among its siblings and leaves the parent Storage where it is.

Snapshots

SNAPSHOT	VOLUME	AGE (DAYS)	SIZE (GB)
snap-001	vol-003	7	10
snap-002	vol-005	14	15
snap-003	vol-007	21	20
snap-004	vol-009	28	25
snap-005	vol-011	35	30
snap-006	vol-013	42	5

SNAPSHOT	VOLUME	AGE (DAYS)	SIZE (GB)
snap-007	vol-015	49	10
snap-008	vol-017	56	15
snap-009	vol-019	3	20
snap-010	vol-021	10	25
snap-011	vol-023	17	30
snap-012	vol-001	24	5
snap-013	vol-003	31	10
snap-014	vol-005	38	15

Storage › Capacity

What you are looking at

The KPI strip above this note was declared once, at the path Storage with -NavScope Subtree, so it appears on every Storage view. The red banner is EXACT to this view. The chart and the table below belong to Storage/Capacity only. The table is last because tables always come after blocks.

Volumes

VOLUME	TIER	SIZE (GB)	USED
vol-001	SILVER	200	23
vol-002	BRONZE	300	26
vol-003	GOLD	400	29
vol-004	SILVER	500	32
vol-005	BRONZE	600	35

VOLUME	TIER	SIZE (GB)	USED
vol-006	GOLD	700	38
vol-007	SILVER	800	41
vol-008	BRONZE	100	44
vol-009	GOLD	200	47
vol-010	SILVER	300	50
vol-011	BRONZE	400	53
vol-012	GOLD	500	56
vol-013	SILVER	600	59
vol-014	BRONZE	700	62
vol-015	GOLD	800	65
vol-016	SILVER	100	68
vol-017	BRONZE	200	71
vol-018	GOLD	300	74
vol-019	SILVER	400	77
vol-020	BRONZE	500	80
vol-021	GOLD	600	83
vol-022	SILVER	700	86
vol-023	BRONZE	800	89
vol-024	GOLD	100	92

Volumes by tier




Storage › Tagging

What you are looking at

A block bound to a second-level node. Its own menu entry exists because an item sits exactly on this path.

Tagged and untagged



Yes	**18** (75%)
No	**6** (25%)

Compute › Hosts

What you are looking at

Two tables share the path Compute/Hosts and are joined with Set-DhTableLink: click a host and the VM table below filters to it. Joined tables belong on ONE path so they stack on one view.

Hosts (click a row)

HOST	CLUSTER	CPU %
esxi-01	dev	37
esxi-02	prod	44
esxi-03	dev	51
esxi-04	prod	58
esxi-05	dev	65
esxi-06	prod	72
esxi-07	dev	79
esxi-08	prod	86

Virtual machines on the selected host

VM	HOST	ROLE	MEMORY (GB)
vm-001	esxi-02	db	8
vm-002	esxi-03	web	12
vm-003	esxi-04	app	16
vm-004	esxi-05	db	20
vm-005	esxi-06	web	24
vm-006	esxi-07	app	4
vm-007	esxi-08	db	8
vm-008	esxi-01	web	12
vm-009	esxi-02	app	16
vm-010	esxi-03	db	20
vm-011	esxi-04	web	24
vm-012	esxi-05	app	4
vm-013	esxi-06	db	8

VM	HOST	ROLE	MEMORY (GB)
vm-014	esxi-07	web	12
vm-015	esxi-08	app	16
vm-016	esxi-01	db	20
vm-017	esxi-02	web	24
vm-018	esxi-03	app	4
vm-019	esxi-04	db	8
vm-020	esxi-05	web	12
vm-021	esxi-06	app	16
vm-022	esxi-07	db	20
vm-023	esxi-08	web	24
vm-024	esxi-01	app	4

Compute › Virtual machines

What you are looking at

A GLOBAL-scope item would appear here too; this chart is Exact, so it does not leave this view.

VMs by role



Generated by **DashHtml** v3.0.0 — 2026-11-02 07:27:44 +01:00 — Feature-Navigation.ps1