


UNIVERSITY OF COPENHAGEN

Experimental Design Recovery: Basic Concepts

PCSD, Marcos Vaz Salles

Do-it-yourself Recap: Virtual Memory with Paging

- How could we build a twolevel memory abstraction out of RAM and disk, with hopefully the latency of RAM and the size of disk?
- How did we handle READ and WRITE? What about page replacement?
- What were the guarantees we got in terms of atomicity and fault-tolerance?





What should we learn today?

- Explain the three main methodologies for performance measurement and modeling: analytical modeling, simulation, and experimentation
- Design and execute experiments to measure the performance of a system
- Explain the concepts of volatile, nonvolatile, and stable storage as well as the main assumptions underlying database recovery
- Predict how force/no-force and steal/no-steal strategies for writes and buffer management influence the need for redo and undo
- Explain the notion of logging and the concept of write-ahead logging



Techniques to Evaluate Performance

- Topic could be a whole course by itself!
 - See refs in syllabus (books by Jain, Lilja)
- Three main techniques
 - Analytical Modeling
 - Simulation
 - Experimentation





Analytical Modeling

- Get intuition about system performance
 - Without actually implementing it!
- Remember our virtual memory system with paging? Simple model:

```
AverageLatency = HitRatio * Latency<sub>Hit</sub> + (1 - HitRatio) * Latency<sub>Miss</sub>
```

- With high hit ratio (say, >95%), average time can be pretty close to main memory
 - Some requests still require going to disk, of course, and take full disk latency blow
- How can we know the hit ratio?



Simulation

- Study properties of hard-to-model process, e.g., locality of workloads vs. hit ratio in cache
- Configure model with known parameters
 - In our example, Latency_{Hit} and Latency_{Miss}
- Simulate behavior of system to get HitRatio



Simulation

Pros

- Effort may be smaller than full-blown implementation
- Allows you to simulate "impossible" or hard-toexperiment-with scenarios → 10Ks of machines, nextgeneration flash disk not on the market yet

Cons

- Estimating parameters
- Validating models and approximations
- Choosing workloads



8

Numbers Everyone Should Know

| L1 cache reference | 0.5 | ns |
|------------------------------------|-------------|----|
| Branch mispredict | 5 | ns |
| L2 cache reference | 7 | ns |
| Mutex lock/unlock | 25 | ns |
| Main memory reference | 100 | ns |
| Compress 1K bytes with Zippy | 3,000 | ns |
| Send 2K bytes over 1 Gbps network | 20,000 | ns |
| Read 1 MB sequentially from memory | 250,000 | ns |
| Round trip within same datacenter | 500,000 | ns |
| Disk seek | 10,000,000 | ns |
| Read 1 MB sequentially from disk | 20,000,000 | ns |
| Send packet CA->Netherlands->CA | 150,000,000 | ns |
| | | |



Source: Dean

Choosing Workloads & Datasets

- Synthetic workloads & datasets
 - Example: Use Zipf distribution to generate workload of page accesses
- Real workloads & datasets
 - Example: Take trace of page requests from real application
 - Replay trace on your simulator
- Combinations also possible
 - Use real dataset but generate accesses using a distribution
- Issue: How can you tell if workload is representative?



Experimentation

- Implement real system or prototype
- Measure how it behaves with experiments
 - Most respected method
 - But also requires most effort
- Profile system to determine where time goes





Simple Factor Experimentation

- Understanding multiple influences
- Vary one factor at a time, keep others fixed
- Example: Skew of workload and size of cache
 - Skew=0.5, vary cache size from 1MB to 1GB
 - Cache size = 500MB, vary skew from 0 to 1
- Care required: Parameters may influence each other!



Benchmarking

Micro-benchmarks

 Measure a specific variable or piece of code, e.g., memory and disk latencies in small experiment to calibrate simulation model

Application-level benchmark

- Whole application designed to stress certain types of systems
- **SPEC** benchmarks for compute-intensive apps, web servers, file systems, and many others
- **TPC** benchmarks for databases



Designing a Micro-Benchmark


- How would you measure file scan performance of your filesystem?
- What performance metric would you measure?
- What are the factors that may affect performance?
- Which simple factor experiments would you use?




Hint: Think about or write down your measurement program!

Necessary Care with Executing Experiments

- Select event counts
 - Number of pages/chunks read
 - Number of clock cycles elapsed → wall-clock time
- But control for overhead of event counting itself!
- Sampling / monitoring
 - e.g., I/O via iostat/vmstat
- "Statistics can prove anything?!" ⊕
 - Number of measurements
 - Mean and variance
 - Confidence intervals
 - Dealing with outliers
 - Setup matters!





Dramatic increase in the amount of untrue statistics...

Comparing Alternatives

- Two systems, with throughput-oriented measurements R₂ and R₁
 - Both systems travel same distance D, i.e., do same work but take different time
 - $R_2 = D / T_2 ; R_1 = D / T_1$
- Speedup

•
$$S_{2,1} = R_2 / R_1 = T_1 / T_2$$

- Relative change
 - $\Delta_{2,1} = (R_2 R_1) / R_1 = S_{2,1} 1$
- Example statements
 - System 2 is 1.4 times faster than System 1
 - System 2 is 40% faster than System 1



Questions so far?




The many faces of atomicity

- Atomicity is strong modularity mechanism!
 - Hides that one high-level action is actually made of many sub-actions
- Before-or-after atomicity
 - == Isolation
 - Cannot have effects that would only arise by interleaving of parts of transactions
- All-or-nothing atomicity
 - == Atomicity (+ Durability)
 - Cannot have partially executed transactions
 - Once executed and confirmed, transaction effects are visible and not forgotten



Implementing All-or-nothing Atomicity

- Atomicity
 - Transactions may abort ("Rollback").
- Durability
 - What if system stops running? (Causes?)
- Desired Behavior after system restarts:
 - T1, T2 & T3 should be durable.
 - T4 & T5 should be aborted (effects not seen).





Assumptions

- Concurrency control is in effect
 - Strict 2PL, in particular
- Updates are happening "in place"
 - i.e. data is overwritten on (deleted from) memory using READ / WRITE interface.
 - We will use a two-level memory with buffer and disk
- Types of failures
 - Crash
 - Media failure
- Always fail-stop!



Volatile vs. Nonvolatile vs. Stable Storage

- Volatile Storage
 - Lost in the event of a crash
 - Example: main memory
- Nonvolatile Storage
 - Not lost on crash, but lost on media failure
 - Example: disk
- Stable Storage
 - Never lost (otherwise, that's it ©)
 - How do you implement this one?



Surviving Crashes: How to handle the Buffer Pool?

Fill in the matrix: When do you need to UNDO changes? When do you need to REDO changes?

- Force every write to disk?
 - Poor response time.
 - But provides durability.
- Steal buffer-pool frames from uncommitted Xacts?
 - If not, poor throughput.
 - If so, how can we ensure atomicity?

Force Trivial (?)
No Force Desired



More on Steal and Force


- **STEAL** (why enforcing Atomicity is hard)
 - To steal frame F: Current page in F (say P) is written to disk; some Xact holds lock on P.
 - What if the Xact with the lock on P aborts?
 - Must remember the old value of P at steal time (to support UNDOing the write to page P).
- NO FORCE (why enforcing Durability is hard)
 - What if system crashes before a modified page is written to disk?
 - Write as little as possible, in a convenient place, at commit time, to support REDOing modifications.



Questions so far?




Undo/Redo vs. Force/Steal



How do we support this option?



Basic Idea: Logging



- Record REDO and UNDO information, for every update, in a log.
 - Sequential writes to log (put it on a separate disk).
 - Minimal info (diff) written to log, so multiple updates fit in a single log page.
- Log: An ordered list of REDO/UNDO actions
 - Logical vs. Physical Logging
 - Example physical log record contains:

<XID, pageID, offset, length, old data, new data>

Good compromise is physiological logging.



Write-Ahead Logging (WAL)

- Golden Rule: Never modify the only copy!
- The Write-Ahead Logging Protocol:
 - 1) Must force the log record for an update <u>before</u> the corresponding data page gets to disk.
 - 2) Must write all log records for a Xact before commit.
- #1 guarantees Atomicity.
- #2 guarantees Durability.
- Exactly how is logging (and recovery!) done?
 - We will study the ARIES algorithms. (next time! ©)



Recovery Equations

Nonvolatile Storage: DB files Stable
Storage:
DB log (online) +
DB backup (offline)

Discussion:

- Crash Recovery: volatile memory lost
 - Current DB = DB files + DB log ______ since when?
- Media Recovery: nonvolatile storage lost
 - Current DB = DB backup + DB log → since when?
- We will focus on crash recovery next



What should we learn today?

- Explain the three main methodologies for performance measurement and modeling: analytical modeling, simulation, and experimentation
- Design and execute experiments to measure the performance of a system
- Explain the concepts of volatile, nonvolatile, and stable storage as well as the main assumptions underlying database recovery
- Predict how force/no-force and steal/no-steal strategies for writes and buffer management influence the need for redo and undo
- Explain the notion of logging and the concept of write-ahead logging

