dim:

To configure wireless LAN using cisco parket traver.

Procedure:

1. Create retwork 3 PCS & a cruireless Poiter

2. Rightlink on the animeless vonter Note the

il Poddress - It would be

192.168.0.1

- > Desable the DHCP server

- Savo Settings

3) dick on wireless on the same page

- drange Network name to

Mehono Vetwork

-) Save setting

-) click on crowneless security under originaless

I change security mode to WEP from

-) Add ckey 1:0123456789

-) Savesettings

-5. Mon close the window

4. Now assign 1 p to the pro

Per=192-168.0.5

-) gaterray - 192. 168.0.1

PC1-192.168.0.6

gate way - (92.168.0.1

P(2-192.168.0.7 gaterway - 192.168.0. a

5) Now which on \$ (0

-) disk physical option

-) training obt that - &

-) orang the part in the diagram

-> to the dept around

-) Drag the 'WN P300 N/ to the part
Green the debt

-) Twen on that

- Now click on desptop of auricless

-> cluk connect -> site anformation ->


J type 0123456789 an the WE + tay,

-) Connect

6) repeat step 5 for the part par

of Then you am see the below connection in

Gogrammali representation



of p: Elmo the parties could be transmitted via

Eire	Last Status	Source	dectination	type	alow	Time	period	fu
0	Successful	PCO	P(2)	ion p	D	0.000	N	0
	Successful				D	0.566	N	1

Event C	Time (are)	Last Deviso
VIS	0.000 0.001 0.003 0.004 0.004 0.004	f C O whales couter o whales touter o wrales router o
	0.005	P(Z wireles vrouter

Student abeservations
a) about is SSID of curineless Pouter?
Aus:

Service set Indutifier is the name assigned to a universess vetwork, allowing devices to undertiby and connect to the covert wist. The SSID is broadcast by the continuary helps distinguish one metwork from other in the same area.

b) what is security chey in wireless router.

A sewrity bey is a passward or lode used to protect a wireless network, ensuring only outhorised users con connect - Common types an WEP, WPA sets

Result:

Thus courseles can dras been configured successfully using cipco parket tracen