

What's New in VisionEval Workbench 2.0

Windows x64 - native runtime edition

VisionEval Workbench 2.0 brings the complete bounded Hypercube workflow to Windows and can either connect to an existing native installation or install the certified R 4.5.3 and VisionEval VE-40-RC7 pair for the current user.

First-run runtime setup

- Detect an existing `VE_RUNTIME`, `VE_HOME`, and `Rscript.exe`, or select each path independently.
- Install the pinned R 4.5.3 and official RC7 Windows library without administrator privileges when no usable runtime is available.
- Keep `VE_HOME`, `VE_RUNTIME`, the application, and the workspace separate. Equal, nested, junction-aliased, and symbolic-link-aliased runtime/home paths are rejected.
- Verify official download SHA-256 values and RC7 `VECommit` package metadata before enabling runs.
- Cancel, retry, or use the documented offline/manual setup path without leaving a partial VisionEval library active.

Hypercube experiments

- Create a dedicated two-axis project and preview every generated case before committing it.
- Run cases through one native VisionEval slot in the common workspace FIFO queue.
- Stop one Hypercube without removing unrelated Standard or Hypercube batches.
- Review one compact Run-history card while retaining detailed case logs on Hypercube → Run.

Analysis and export

- Build cached Response Matrices with explicit aggregation and instant cell selection.
- Find changes across every verified completed case with independent Year and Aggregation controls.
- Rank outputs or scenarios, inspect zero-baseline results, and open scenario details without recalculating.
- Export the baseline or up to three completed cases as separate ZIP packages containing resolved inputs, temporary output CSVs, and a manifest—never the Datastore.

Reliability and Windows behavior

- Standard and Hypercube batches share a persistent FIFO queue and recover accurately after restart.
- Workspace leases prevent two backends from controlling the same workspace.
- Active R process trees are stopped with Windows-native cleanup before partial files are removed.
- The Windows edition is native-only: it does not require or activate Docker. The optional managed installer changes only the selected current-user R, `VE_HOME`, and `VE_RUNTIME` locations after explicit approval.
- Hypercubes are safe on laptops. Systems below 16 GB of RAM receive advisory guidance, while low workspace capacity produces a confirmation warning rather than an automatic block.