

➤ **Oracle Fusion SCM – PIM Series(Part 2)**
setup of Item Statuses for OPPO Enterprise

➤ **Prepared by: [Chinna Narasimhulu Gadena]**

➤ **Introduction :**

In Oracle Fusion PIM, Item Statuses define the current state of an item (example: Development, Active, Inactive).

Each status controls which functions are enabled or disabled for the item during its lifecycle.

📌 Note: Oracle provides some default statuses (like Active, Inactive, Development).


For learning purposes, I created my own custom status (OPPO Status) so I can use it in all my examples consistently.

➤ Navigation to Manage Item Statuses

Step 1: Navigate to Manage Item Types

From the Home Page, go to:

→ Settings and Actions → Setup and Maintenance




This is where you access Setup and Maintenance to start configuration.

Step 2: Search Task

In the Setup and Maintenance screen


→ Search for Manage Item Statuses.



This task allows us to create and manage Item Statuses.

After opening, you will see a list of default statuses (Active, Development, Inactive).

To add a new status, click on the “+” symbol on top.



Code	Name	Description	Inactive Date
Active	Active	All functions Enabled	
DEV	Development	Development - Sales Orders Not Enabled	
Inactive	Inactive	All functions Disabled	

Here we can see Oracle defaults and OPPO-specific statuses

➤ Creating OPPO Active Status


Fill in the details for the new status as follows:

Code: OPPO

Name: OPPO Stats

Description: Items are ready to sell

Functions: All enabled



Create Item Status

* Code

* Name


Description

Inactive Date

Status Attributes

Attribute Group	Attribute	Attribute Value	Us

After Entering all Values our Example OPPO-specific status (Oppo Active) for training purposes



Key Takeaways

Item Statuses help control item usage at each lifecycle stage

Common ones: Development → Active → Inactive.

Custom statuses like OPPO Active allow flexibility for practice and business scenarios.

Next Steps in PIM Series:

And next parts, we will configure:

Part 3: Item Life Cycle Phases

Part 4: UMO

Part 5: Item Classes

Part 6: Item Catalogs

Part 7: Item Categories.

