


Read the Instruction Carefully Regarding How you need to Access the Rack and What You need to do from your end before starting configuration.

Note: Before each session, you will receive the username and password, along with the rack number you need to access. The assigned rack can be Rack 1, Rack 2, Rack 3, or Rack 4.

Step 1:- You need to take the RDP using any software with respect to your operating system compatibility. For windows you can use Remote Desktop Connection



An IP address needs to be assigned to the Computer option. To find the correct IP address, refer to the Rack Detail Document and **assign the IP address corresponding to the rack assigned to you.**

Username and Password will be shared before your session.


Step 2:- After logging in via RDP, open a browser on the RDP machine and refer to the Rack Detail PDF to find the ESXi IP address, username, and password for your assigned rack. Log in to the ESXi server and revert the snapshot of each virtual machine to restore the lab environment to its required state.

All virtual machines, except DNAC, will be hosted on **ESXi 1**. The DNAC virtual machine will be hosted on **ESXi 2**.

Login into the **ESXi 1** and Revert the snapshot of All the Devices **Except AD-DNS, R2 and Mail Server Cisco (Do not Touch and Revert the Snapshot of these 3 devices)**.



How to Revert the Snapshot of Each Device.

For Virtual Machines, Once you will inside the **ESXi 1**. Right on the Device and Go to the Snapshot and Click Restore the Snapshot as shown in Picture below.




Note:- In the same way, revert the snapshot of each device one by one, except AD-DNS, R2, and Mail Server, as shown in the figure above.

[For Cisco ISE](#), after reverting the snapshot, power off the ISE virtual machine and then power it back on as shown in Picture below. Allow approximately 15 minutes for the ISE services to start. After that, the ISE GUI should be accessible.




For DNAC, the same procedure used to restore the virtual machine on ESXi 1 should be followed on ESXi 2 to restore the snapshot of the DNAC virtual machine.



Note: After restoring the snapshots of all devices, except AD-DNS, R2, and Mail Server, wait approximately 10 minutes to allow all processes and services to stabilize.



Note:- You can access ESXi 1 and ESXi 2 using the IP address, username, and password provided in the Rack Detail PDF. For your convenience, we have also bookmarked all the required ESXi servers in Firefox on the RDP machine, and the passwords have been saved in the browser. You can access the ESXi servers directly using these bookmarks.



Step 3:- How to Access the Network Device and Pc.

For Network Devices:

To access the network devices, use SecureCRT, which is pinned to the taskbar of the RDP machine. Click on the SecureCRT icon to open it as shown in Picture Below.



Note:- Double Click on the Particular network device to do the configuration

For EndPoint (PC):


To access the PC, use mRemoteNg, which is pinned to the taskbar of the RDP machine. Click on the mRemoteNG icon to open it as shown in Picture Below.




Note:- Double Click on the Respective PC to Open that PC. One example:- Suppose if you need to go inside mgmt_pc (Management_PC) Double Click on that particular PC inside mRemoteNG then that PC will be accessible.

Key Point

Point 1:- If sometime the **Mgmt-PC** is not working properly or becomes slow, you can use the **RDP machine as an alternative management PC**. You can perform most of the tasks that are normally performed on the Mgmt-PC from the RDP machine, including accessing and configuring ISE, FMC-FTD, FMC-NGIPS, and WSA.





Point 2:- Sometimes, after restoring the EVE-NG snapshot from ESXi 1, you may encounter an issue where a device does not boot properly, as shown in the figure below.



For routers and switches (except ASA), if a device remains stuck in the state shown in the picture above, login in to EVE-NG, locate the affected device, right-click on it, and select Stop. Then, start the device again as shown in the figure below.

To login Eveng Go to <http://150.1.7.20> and Login username:- admin and password:- eve.



For the ASA, if the CLI does not open even after waiting 10-15 minutes following the snapshot restoration, or if the ASA becomes stuck after changing its mode and the CLI is no longer accessible, restore the EVE-NG snapshot from ESXi 1 again.

