


COSMOS / Keyboard + Hyprrland

Repository keymap · Hyprrland reviewed 2026-09-30 · large / 2 per page
Keymap bottom: hold/sticky. Hyprrland bottom: Base key; top: +Shift. Pink: hold; dashed: optional Shift.

Base · typing and thumb keys




Center = tap; bottom = hold / sticky modifier

Enter/Super and Backspace/Raise: hold 200 ms. Tab/Lower: chord for immediate Lower. J+K = Escape.

Sticky Alt/Ctrl/Shift/Func: tap for the next key, or hold. Use left Alt and outer left Shift.

Lower · numbers and symbols



Hold the left inner Tab / Lower thumb


Chord Tab/Lower for immediate symbols; tap alone for Tab. For fast Tab → letter, use top-left Tab.

▽ means the layer underneath. For one-shot Func, press modifiers before tapping Func.

COSMOS / Keyboard + Hyprrland


Repository keymap · Hyprrland reviewed 2026-09-30 · large / 2 per page
Keymap bottom: hold/sticky. Hyprrland bottom: Base key; top: +Shift. Pink: hold; dashed: optional Shift.

Raise · navigation and media



Hold the right inner Backspace / Raise thumb
I/J/K/L = ↑/←/↓/→. Raise+H latches scrolling after release; any next key/button press cancels.
Esc/Ctrl thumb: tap Escape, hold Ctrl. Pause after a Backspace tap before holding for Raise.

Func · function keys and utilities




Tap Func for the next key; hold for several actions
Fn+N unlocks Studio. Fn+B / Fn+Slash enters the left / right bootloader.
Private unlock: hold physical Fn+J+K+L for 2 s; requires USB and a provisioned right half.

COSMOS / Keyboard + Hyprrland


Repository keymap · Hyprrland reviewed 2026-09-30 · large / 2 per page
Keymap bottom: hold/sticky. Hyprrland bottom: Base key; top: +Shift. Pink: hold; dashed: optional Shift.

Super · workspaces and launcher



Hold Enter / Super; top legends add Shift
Move 1-10 moves the window and follows. Magic = special:magic. Z actions on G fire on release.
Sets = the monitor-dependent workspace-set helper. Resolve the Super hold before the action key.

Alt · applications and window groups




Hold LEFT Alt; top legends add Shift
Parent selects the enclosing group; Flip grp changes its orientation. Term. = terminal.
For Terminal, tap Enter while holding Alt. Alt+Shift+Space toggles Waybar.

COSMOS / Keyboard + Hyprrland

Repository keymap · Hyprrland reviewed 2026-09-30 · large / 2 per page

Keymap bottom: hold/sticky. Hyprland bottom: Base key; top: +Shift. Pink: hold; dashed: optional Shift.

Alt + Raise · focus, move and resize




Hold left Alt + Backspace / Raise;
top legends add Shift

Add outer Shift for smart window movement or height resize. Smart move can cross monitor edges.

Resize: physical D/F (minus/equal),
100 px per tap. Retap directions
for repeated focus/move.

Alt + Lower · numeric workspaces



Hold left Alt + Tab / Lower; top legends add Shift


Physical A S D F G H J K L Quote =
1-10. Add outer left Shift to move
the window and follow.

The right Shift thumb sends colon on Lower. Super + Q-P is the simpler workspace shortcut.

COSMOS / Keyboard + Hyprrland

Repository keymap · Hyprrland reviewed 2026-09-30 · large / 2 per page
Keymap bottom: hold/sticky. Hyprrland bottom: Base key; top: +Shift. Pink: hold; dashed: optional Shift.

Raise · physical-key reference




Hold Backspace / Raise; bottom legends identify Base keys

Raise+H latches scrolling; any next key/button press cancels. Super + scrolling changes workspace.

Drag/resize: release Raise, hold left Alt + left/right microswitch, and roll the trackball.

Deck · Super + Raise navigation



Hold Enter / Super + Backspace / Raise; top legends add Shift

Super+arrows focuses; add Shift to move via hy3 directly, without the smart-move fallback.

Super+Escape lock and Super+Shift+Escape exit are unbound on Deck; use the rail lock button.