
COSMOS / Keyboard + Hyprland

Repository keymap · Hyprland reviewed 2026-10-03 · large / 2 per page

Keymap bottom: hold/sticky. Hyprland bottom: Base key; top: +Shift. Pink: hold; dashed: optional Shift.

Base · typing and thumb keys




Center = tap; bottom = hold / sticky modifier

Super: hold 200 ms. Lower/Raise: immediate key chords; 200 ms when held alone. J+K = Escape.

Sticky Alt/Ctrl/Shift/Func: tap for the next key, or hold. Use left Alt and outer left Shift.

Lower · numbers and symbols



Hold the left inner Tab / Lower thumb

Chord Tab/Lower for immediate symbols; tap alone for Tab. For fast Tab → letter, use top-left Tab.

▽ means the layer underneath. For one-shot Func, press modifiers before tapping Func.


D = Deck only · Z = zuffie only · ▽ = transparent · Details: HYPRLAND.md · Print A4, actual size (100%).

COSMOS / Keyboard + Hyprland

Repository keymap · Hyprland reviewed 2026-10-03 · large / 2 per page

Keymap bottom: hold/sticky. Hyprland bottom: Base key; top: +Shift. Pink: hold; dashed: optional Shift.

Raise · navigation and media




Hold right thumb Backspace / Raise; another key activates Raise immediately

I/J/K/L = ↑/←/↓/→. Raise+H latches scrolling after release; any next key/button press cancels.

Esc/Ctrl thumb: tap Escape, hold Ctrl. Pause after a Backspace tap before holding for Raise.

Func · function keys and utilities



Tap Func for the next key; hold for several actions

Fn+Quote: region capture. Add Shift: window; Ctrl: output; Alt: color. Hold modifiers before tapping Fn.

Fn+N unlocks Studio. Fn+B / Fn+Slash enters the left / right bootloader.

Private unlock: hold physical Fn+J+K+L for 2 s; requires USB and a provisioned right half.


D = Deck only · Z = zuffie only · ▽ = transparent · Details: HYPRLAND.md · Print A4, actual size (100%).

COSMOS / Keyboard + Hyprland

Repository keymap · Hyprland reviewed 2026-10-03 · large / 2 per page

Keymap bottom: hold/sticky. Hyprland bottom: Base key; top: +Shift. Pink: hold; dashed: optional Shift.

Super · workspaces and launcher




Hold Enter / Super; top legends add Shift

Move 1–10 moves the window and follows. Magic = special:magic. Z actions on G fire on release.

Sets = the monitor-dependent workspace-set helper. Resolve the Super hold before the action key.

Alt · applications and window groups



Hold LEFT Alt; top legends add Shift

Parent selects the enclosing group; Flip grp changes its orientation. Term. = terminal.

For Terminal, tap Enter while holding Alt. Alt+Shift+Space toggles Waybar.


D = Deck only · Z = zuffie only · ▽ = transparent · Details: HYPRLAND.md · Print A4, actual size (100%).

COSMOS / Keyboard + Hyprland

Repository keymap · Hyprland reviewed 2026-10-03 · large / 2 per page

Keymap bottom: hold/sticky. Hyprland bottom: Base key; top: +Shift. Pink: hold; dashed: optional Shift.

Alt + Raise · focus, move and resize




Hold left Alt + Backspace / Raise; top legends add Shift

Add outer Shift for smart window movement or height resize. Smart move can cross monitor edges.

Resize: physical D/F (minus/equal), 100 px per tap. Retap directions for repeated focus/move.

Alt + Lower · numeric workspaces



Hold left Alt + Tab / Lower; top legends add Shift

Physical A S D F G H J K L Quote = 1–10. Add outer left Shift to move the window and follow.

The right Shift thumb sends colon on Lower. Super + Q–P is the simpler workspace shortcut.


D = Deck only · Z = zuffie only · ▽ = transparent · Details: HYPRLAND.md · Print A4, actual size (100%).

COSMOS / Keyboard + Hyprland

Repository keymap · Hyprland reviewed 2026-10-03 · large / 2 per page

Keymap bottom: hold/sticky. Hyprland bottom: Base key; top: +Shift. Pink: hold; dashed: optional Shift.

Raise · physical-key reference




Hold Backspace / Raise; bottom legends identify Base keys

Raise+H latches scrolling; any next key/button press cancels. Super + scrolling changes workspace.

Drag/resize: release Raise, hold left Alt + left/right microswitch, and roll the trackball.

Deck · Super + Raise navigation



Hold Enter / Super + Backspace / Raise; top legends add Shift

Super+arrows focuses; add Shift to move via hy3 directly, without the smart-move fallback.

Super+Escape lock and Super+Shift+Escape exit are unbound on Deck; use the rail lock button.

D = Deck only · Z = zuffie only · ▽ = transparent · Details: HYPRLAND.md · Print A4, actual size (100%).