Trace+
for Adobe Premiere Pro


Installing Trace+

Two steps. It installs alongside Trace and replaces nothing.

Trace scans a clip. Trace+ scans the entire project.

1 Download the file and double-click it


Check your email and press My orders to find your download links and licence key. Download Trace-Plus.ccx and double-click it — Creative Cloud Desktop installs it for you. The guide you are reading is the other file.



Your order — download Trace-Plus.ccx, then double-click it

2 Restart Premiere Pro

Quit Premiere and open it again. Premiere only looks for new panels at startup. You need Premiere Pro 25.6 or newer.




Creative Cloud Desktop says Installed — now restart Premiere

© NK Courses 2026. All rights reserved.

3 Open the panel


Window > UXP Plugins > Trace+. Installing this does not touch the free panel — it gets its own entry, next to Trace's. Trace+ does everything Trace does, so you can remove Trace whenever you like: Window > UXP Plugins > Manage Plugins.



Window > UXP Plugins > Trace+

4 Find what you are not using

With nothing selected, press Project on the toolbar, then Not used on the switch above the list. Trace+ reads every bin — not just the timelines — and tells you what is on no timeline at all, what it would weigh, and what is only used in archived cuts. Nothing is moved and nothing is deleted.



Project, then Not used — every bin, weighed

Why the number is lower than you expected


Media you use through a subclip is never counted as unused.
If any project item pointing at a file is on a timeline, that file is in use — even when the master clip itself was never cut in. Those items are listed separately, as clutter.

Sequences are left out entirely.
A finished film is not nested inside anything, so by the obvious test every deliverable you have ever made would count as unused.

© NK Courses 2026. All rights reserved.

5 Paste your licence key

Menu > About / Licence. Paste the key from your order email and press Activate — the panel unlocks straight away and there is nothing to restart. One key runs on two machines: a desktop and a laptop, or work and home. Changing computer? Press Remove on the one you are leaving behind and the seat is free immediately.



Paste your key and press Activate

If something doesn't go to plan

Trace+ isn't in the Window menu.
Look under Window > UXP Plugins, not Window > Extensions. If UXP Plugins is not there at all, Premiere is older than 25.6.

The key was refused.
Re-copy it — a trailing space is the usual culprit. If both seats are in use, press Remove on a machine you no longer use.

It found less than I expected.
See page 2. Trace+ would rather under-report than tell you to archive footage you are still using.

Still stuck?

Email support@nkcourses.co.uk, or reply to your receipt. I'm one person, so it might take a day — but it will be me answering. Open the panel menu and choose Scan report first — it copies itself to your clipboard, and it usually tells me what happened without a single question back.