Quick start instructions for Echoview cloud license access

This document is a modified version of Echoview's "Quick Start Guide" with annotations and troubleshooting instructions.

Accessing your Echoview cloud license

- Using an Echoview cloud license requires an initial setup process outlined below.
- Following this process, a secure connection will be stored on your device.
- After the setup, starting Echoview while connected to the internet will use your Echoview cloud license without any further steps.

Before you begin:

- Confirm that the device you intend to license is connected to the internet and that Echoview has been installed
- Remove any Echoview dongles (USB licenses) from your device

Initial Setup

Set your initial password

- Each FMC (aka Science Center) will have an Echoview license admin. Contact your admin for a license.

FMC	**Admin POC**	**E-mail address**
AFSC	Rick Towler	Rick Towler - NOAA Federal
NEFSC	Mike Jech	Michael Jech - NOAA Federal
NWFSC	Beth Phillips	Elizabeth Phillips - NOAA Federal
PIFSC	Reka Domokos	Reka Domokos - NOAA Federal
SEFSC	Tim Rowell	Timothy Rowell - NOAA Federal

SWFSC	Josiah Renfree	Josiah Renfree - NOAA Federal

- Once you are provided with an Echoview cloud license, click your unique link sent within an email from support@echoview.com, and follow the prompts to set up your initial password.
    - If you cannot find the email from Echoview support, please check your spam or junk mail folder.
- Setting up your password only needs to be completed once.
- Note: Your link will expire in 3 days
    - This is an easy process and can be done “stand alone”, i.e., you do not need to complete all the other steps at this time - so don’t delay.
- When you have your account, you can use it on all devices.

Connecting to your cloud container

You can connect as many devices as you need to the cloud license.

On each device to be connected to your Echoview cloud license:

1. Open a web browser and navigate to https://lc.codemeter.com/94047/portal/index.php
2. Enter your email address and password, then click Login
    2.1. The “My Licenses” page will be displayed
3. ****Very Important**** A browser permission prompt will most likely appear for lc.codemeter.com that will ask whether to allow codemeter access to other apps on your computer -**select Allow**! Otherwise, see step 4.5.
4. Click *My CmContainers*
    4.1. The *My CmContainers* page will list all containers that you have access to
    4.2. Click the *Connect CmCloudContainer* (icon) displayed to the right of a listed container
    4.3. A *Connect CmCloudContainer* window will be displayed.
    4.4. After a short period of time the message License transfer completed successfully! should be displayed.
    4.5. An error message may be shown if “Allow” (step 3) was not selected at the browser permission prompt.
        4.5.1. If this occurs:

4.5.1.1. Right click on the site controls icon ( ) immediately to the left of the URL in the menu bar ().

4.5.1.2. Click on the radio/slider button to the right of the “Apps on Device” item. It should turn from gray to bright blue.

4.6. Click OK

5. Run Echoview. Echoview should now be successfully licensed via your Echoview cloud license.
   5.1. To confirm, navigate to Help -> License Information. You should see the cloud license. Sometimes it can take a few seconds to connect.

   5.2. You’ll also see the license information in the top banner of your Echoview window.

6. Following successful connection, you will only need to access the License Portal website in the following situations:
   6.1. Your license administrator has reset the container
   6.2. The secure connection has been removed from your device
   6.3. If you would like to connect via a different device

Remove an “old/outdated” cloud license

- If you have an older cloud license, e.g., the temporary cloud license provided by Echoview that expired at the end of September 2026, you can remove it by running the batch file:
  - CodeMeter_DeleteSpecificCmCloudCredentials_EC202605_(NOAA_NEFSC).bat

- This batch file is specific to the temporary license! You should contact Echoview support (support@echoview.com) to modify the file for another license.

- This batch file is located in the AA-SI Echoview GitHub docs repository.

- To run it, you’ll need to copy the .bat file to your Windows VM/workstation.
  - An easy way to copy is to use a web browser (most likely Chrome if you’re on a Fisheries PC/VM) to navigate to the docs repository (linked above) and download the file to your PC/VM (it may default to the Downloads directory).

- Confirm that the license was removed by

- clicking on the codemeter icon (), which is found on the right side of the task tray using the up-arrow/caret icon (

) or
- Running Echoview and checking the license.