



Echoview cloud licenses: Setup and use

The following instructions guide you through the setup and use of your Echoview cloud license.

This process must be completed on each computer that you wish to access the license from. Your computer must be connected to the internet during setup and whenever the license is in use.

Along with these instructions, we will provide you with a link to download a *.wbc file. This file contains your *cloud credentials*, which allow you to access your cloud license.

Important: Anyone who imports this cloud credentials file will have access to your license. Only share the file with authorized users.

Setup instructions

1. Install **Echoview 16** directly from [this link](#), or by downloading from the [Echoview website](#), or using the [Echoview Software Updater](#).
2. Download the *.wbc (cloud credentials) file to your computer.
3. Remove any Echoview dongles (USB licenses) from your computer.
4. In the Windows **Start** menu, navigate to **All** apps, then the **CodeMeter** program folder, and click **CodeMeter Control Center**.
5. On the **File** menu, click **Import License...**
6. Locate and select the *.wbc file that you saved, and click **Import**.
7. Close the **CodeMeter Control Center**.
8. Start **Echoview**. Your cloud license details can be confirmed by opening the **Help** menu and clicking **License Information**.

Ongoing use

- The cloud credentials file can be imported to multiple devices, but concurrent access is limited to the number of seats purchased.
- We recommend saving a copy of the cloud credentials file in a secure, backed up location for future use.
- If all license seats are in use, Echoview will display a message stating that "no more seats are available".
- Contact info@echoview.com if:
 - Your cloud credentials or licenses are compromised and you therefore require the license to be reset (e.g., if someone leaves employment at your organization but still has access to the license on a personal device). A license reset will require all authorized users to manually remove the existing license and then repeat steps 2-8 using a new cloud credentials file.
- Contact support@echoview.com if:
 - You are using the Windows Server operating system, and encounter issues (additional drivers may need to be installed)
 - You need instructions to manually remove cloud license access from a computer.
 - You lose your backup copy of the cloud credentials file.
 - You encounter any unexpected licensing errors when importing the cloud credentials file or using Echoview. If so, please include a screenshot of the error in your email.
- Additional features (such as user management) are anticipated in future updates to Echoview's cloud licensing system.