

If the agent is not installed you can skip step 1 and continue with step 2.

If agent is installed already and not in the Reported Systems Sheet You need to follow all three steps.

Step 1 Uninstalling agent.

- Login as a root user or Administrator user.
- Open Terminal and run “**cd /**” command.
- Run “**ll**” command.

```
administrator@ntp-9345:~$ cd /
administrator@ntp-9345:/$ ll
total 2131376
drwxr-xr-x 25 root root      4096 Oct 27 17:01 ./
drwxr-xr-x 25 root root      4096 Oct 27 17:01 ../
drwxr-xr-x  2 root root      4096 Sep 19  2019 bin/
drwxr-xr-x  4 root root      4096 Jun 22  2019 boot/
drwxrwxr-x  2 root root      4096 Jun 22  2019 cdrom/
drwx----- 3 root root      4096 Jul  3  2019 .config/
-rw-----  1 root root    34926592 Feb 11  2021 core
drwxr-xr-x 19 root root      4580 Oct 27 09:39 dev/
drwxr-xr-x 131 root root     12288 Oct 10 15:59 etc/
drwxr-xr-x  4 root root      4096 Feb 10  2021 home/
lrwxrwxrwx  1 root root         33 Jun 22  2019 initrd.img -> boot/initrd.img-4.18.0-15-generic
lrwxrwxrwx  1 root root         33 Jun 22  2019 initrd.img.old -> boot/initrd.img-4.18.0-15-generic
drwxr-xr-x 22 root root      4096 Jul  3  2019 lib/
drwxr-xr-x  2 root root      4096 Feb 10  2019 lib64/
drwx----- 2 root root     16384 Jun 22  2019 lost+found/
drwxr-xr-x  4 root root      4096 Feb 10  2021 media/
drwxr-xr-x  2 root root      4096 Feb 10  2019 mnt/
drwxr-xr-x  8 root root      4096 Feb 10  2021 opt/
dr-xr-xr-x 353 root root         0 Oct 27 09:39 proc/
drwx----- 8 root root      4096 Feb 11  2021 root/
drwxr-xr-x 28 root root       800 Oct 27 09:44 run/
drwxr-xr-x  2 root root     12288 Sep 19  2019 sbin/
drwxr-xr-x 18 root root      4096 Oct  6  2022 snap/
drwxr-xr-x  2 root root      4096 Feb 10  2019 srv/
-rw-----  1 root root    2147483648 Jun 22  2019 swapfile
dr-xr-xr-x 13 root root         0 Oct 27 16:58 sys/
drwxrwxrwt 18 root root      4096 Oct 27 17:02 tmp/
drwxr-xr-x 10 root root      4096 Feb 10  2019 usr/
drwxr-xr-x 15 root root      4096 Feb 10  2021 var/
lrwxrwxrwx  1 root root         30 Jun 22  2019 vmlinuz -> boot/vmlinuz-4.18.0-15-generic
```

- Run “**cd /usr/local/manageengine/uems_agent**” command.
- Run “**sudo chmod +x RemoveUEMSAgent.sh**” Command & enter the password.
- Run “**sudo ./RemoveUEMSAgent.sh**” Command. And the agent will be uninstalled.

```
administrator@ntp-9345:/$ cd /usr/local/manageengine/uems_agent/
administrator@ntp-9345:/usr/local/manageengine/uems_agent$ sudo chmod +x RemoveUEMSAgent.sh
[sudo] password for administrator:
administrator@ntp-9345:/usr/local/manageengine/uems_agent$ sudo ./RemoveUEMSAgent.sh
Uninstalling UEMS Agent
Removing Agent Contents
Agent Uninstalled Successfully!
administrator@ntp-9345:/usr/local/manageengine/uems_agent$
```

Step 2 Changing Hostname.

Login as a root user or Administrator user.

1. Open terminal, Run `hostnamectl`
2. It will show the Hostname

```
marko@test-main:~$ hostname
test-main
marko@test-main:~$
```

3. Run `sudo hostnamectl set-hostname 9951-NOD-1234` (add the correct hostname/Asset ID)
And type the password.


```
marko@test-main:~$ hostnamectl set-hostname ubuntu-machine
marko@test-main:~$ hostnamectl
Static hostname: ubuntu-machine
Icon name: computer-vm
Chassis: vm
Machine ID: 31a506bc36354a12a05acf6902bb8bfa
Boot ID: fd3eac7f0ae64c8a8e90b0dc06498ab5
Virtualization: oracle
Operating System: Ubuntu 20.04.1 LTS
Kernel: Linux 5.4.0-52-generic
Architecture: x86-64
marko@test-main:~$
```

Reboot the system after Changing Hostname.


or

The Ubuntu GUI also provides a way to edit the system hostname:

1. First, navigate to Settings > About.




2. Now, locate the Device Name field.



3 Clicking the Device Name field opens the Rename Device dialogue box.


4. In the Rename Device dialogue box, replace the current hostname with a new one and confirm your choice by clicking the Rename button. This action permanently changes the hostname.




Step 3 Installing Agent

Guidelines for the installation of Manage Engine Agent on UBUNTU Desktop PCs


1. Login in the Desktop PC as “**Administrator**”
2. Copy and Paste the below mentioned URL in a browser and hit Enter Key.
<https://drive.google.com/file/d/1bRx8xd3EK8LNS3xrd2LMH9q1enATdIQi/view?usp=sharing>
3. A Google Drive page will show up .
4. Click on “**Download Button**” placed at top right corner.




5. Then click on “**Download Anyway**” button.




6. Then click on “**Save**” button.




7. Then go to “Downloads” folder. (**Desktop** > Click on “**Files**”)




8. Then Click on “**Downloads**”




9. Right click on the zip file “**ManageEngineAgentInstallationFiles.zip**” and select “**Extract Here**” option




10. Double click on the newly extracted folder “**ManageEngineAgentInstallationFiles**”




11. Again Double click on the folder “**LinuxAgent_LocalOffice_UEMSLinuxAgent**”




12. Right click anywhere on the white space and select “**Open in Terminal**” option




13. In the newly opened terminal, type “**sudo su**” and hit the Enter Key.




14. Then input the Administrator's password and hit the Enter Key.




15. Type "ls -lrt" and hit the Enter Key. Make sure that all 5 files are listed as shown below.




16. Then Type “**chmod +x UEMS_LinuxAgent.bin**” and hit the Enter Key.



17. Finally type “**./UEMS_LinuxAgent.bin**” and hit the Enter Key



18. After few minutes a confirmation message “UEMS Agent has been Installed Successfully!” will get as shown below.



Done !

The agent has been successfully installed in the PC.