

System Requirements

1. Networking

The program requires a stable TCP/IP network installation. The IP address of the server must be fixed. It is preferable that the IP address of the clients is fixed also to optimize the performance of the network. Other network protocols may be installed such as NetBEUI or IPX/SPX but this may slow down the network because of the additional performance overhead.

2. Operating System

The server must have a Win2000/XP operating system if it is going to control more than 20 client machines. Otherwise Win98SE/ME may be used. The client may have any of the following operating systems - Win95/98/98SE/ME/2000/XP.

3. Hardware

The server must be of reasonably powerful hardware (PIII-1GHZ CPU above). If the Server operating system is Win2000/XP, the memory requirement is at least 128 MB memory. 256 MB is recommended. A network card is required for the server whether used as standalone or client/server scenario since the product registration is based on the network card.

Server Installation

The steps to proper installation are as follows:

1. Fix the Server IP

Properly configure the TCP/IP network - fix the IP address of the server (ex. 192.168.XXX.XXX). Preferably, fix the IP address of the client machines for better performance.

2. Install the Server

Setup the server first. Insert the installer CD. When the autorun program has run, click on the '*Install Server*' button to install the program.

3. Install the Data Components

The Data Components installer is an optional installation of the server program. Install these components for better performance and robust storage. When installed, '*sentinel.mdf*' and '*sentinel.ldf*' are copied to the application folder. Then the following are installed: MDAC2.5 and MSDE2000 database engine. If you should ever manually install the MSDE2000 setup program, run the command line "[d:\DataComponents\MSDE2000\Setup.exe SECURITYMODE=SQL](#)".

4. Register the Server

When running the server program for the first time, you will be prompted to register the program. Write down the product number and the max client count. An appropriate registration key will be provided by the vendor given then above information. Keep this key in a safe place. To reinstall the server program, you will be required to provide this registration key. Also remember to always use the identical network card because then product number is based on the hardware of the network card.

For a demo registration, choose *Full Demo* as the server edition. This registration will work for 7 days and a maximum of 100 client pcs. Again the registration is based on the network card so do not change your hardware. Also the registration is date dependent so you must enter the product key on the day the registration number was issued. Do not adjust your clock backwards after registration so make sure the system date is correct before installation

5. Enter the User Password

When prompted for the login, type '*admin*' as the user and '*supervisor*' as the password.

6. Server Demo Expiration

When the server demo period expires, you may remove all the client programs as follows. Run the server program. When the registration screen appears, you may purchase the program from the vendor and register the server or you may click the *Unregister button* to disable all the client programs. To manually disable the client from the client program, type *Shift+Z* and login as user '*admin*', password '*supervisor*'.

Client Installation

1. Setup Client DNS and Gateway

If the client IP address is fixed, to allow internet connection sharing, each client machine must be configured as follows:

- a. Open the *control panel*, choose *network*, select the *configuration tab* and choose the *TCP/IP adapter*.
- b. Select the *DNS Configuration* tab and choose *enable DNS*. Then configure the *host* to be the computer name of the client machine. Configure the *DNS server* to be the IP address of the machine with internet access.
- c. Select the *Gateway tab* and add a new gateway to be the IP address of the DNS server. (same above)

2. Test the Server Network Connectivity

When installing the clients, make sure the server program is running and visible over the network. To test the network connectivity, choose run command from the windows start menu. Type '*ping 192.168.XXX.XXX*' (to determine the correct IP address of the server, type '*winipcfg*' or '*ipconfig /all*' on the run command).

3. Install the Client

Insert the installer CD. When the autorun program has run, click on the '*Install Client*' button to install the program. Or manually run the '*d:\Client\Setup.exe*' program. After setup, run the client for the first time from the windows start menu.

4. Configure the Client

When you run the client for the first time, it will self configure. Two pieces of information are required 1.) the 'Station number' which is a NUMERIC designation of the particular workstation and 2.) the Server IP address.

If your computers hostname has a number at the end, the program will use that number, otherwise you will be required to enter a '*station number*' (ex. 15) to identify the client machine. Next you will

be prompted to autodetect the server, if you choose *No*, you must supply the IP of the Server (ex. 192.168.XXX.XXX). Check the *use static address* setting unless you are supplying a hostname instead.

5. Disable the Client

To manually disable the client program, type *Shift+Z* when the client shield program is active and login as user '*admin*', password '*supervisor*'. To enable the client, just run the program from the start menu.

Applying a Manual Patch

To patch the server/client program, stop the program and execute the patch downloaded from the <http://www.onewebnetworx.com> website. When prompted for an install location, just accept the default folder "c:\".

Configuration

All configuration can be set from the *Admin menu - Options menu item*.

To configure the server, you must be logged in with an administrator account (the default administrator account is '*admin*' with password '*supervisor*'). All configuration options is accessed from the admin menu, server options menu item. From the server options form, you can configure security, locking behavior, desklock, rates, sale and expense items, receipt printing, wallpapers, etc...

To configure the client, you must key in *Shift+A* and login with an administrator account. When shown the *main menu*, click on the *Options button*. You will be able to configure the IP address of the server and the station number.

Rates Tab

Rental rates may be configured to adopt to most scenarios. A minimum charge or duration may be set. Charged amount may be rounded say by one or five. Duration may be rounded say by 15 minutes or by hour. Free minutes may be automatically set for the user. Paused duration may be limited to say 5 minutes. A rate may be set for per hour, 45 minutes, half hour, 15 minutes and per minute duration of use. Rental accounts may be defined to differentiate reason of use (ex. games, internet, error, attendant1, attendant2). Rental accounts may be password protected. Discounts may be defined for access at predefined periods or day of the week.

Under the Rental Accounts button, you can set the rates for specific rental account types ex. GAMING or INTERNET. Check internet if the user will be allowed to access internet programs. Check allow remote logon if you want the user to be able to login remotely from the client machine with this rental account.


Under Sales button you can set items that you sell and want to maintain inventory count of.

Receipt Printing button allow you to customize printed receipts.

Block charging rounds charged duration by the number specified. For example if it was set to 15 minutes, 43 minutes will be rounded to 45 minutes and 65 minutes will be rounded to 75 minutes being multiples of 15. As another example, if it was set to 30 then 43 minutes will be rounded 60 minutes and 75 will be rounded to 90 minutes. Rounding grace period provides for an allowance to rounding, say if it was set to 2 minutes, and block charging to 15 minutes then 31 will be rounded to

30 minutes while 34 will be rounded to 45 minutes. For prepaid, block charging and rounding grace period must be set to 0 minutes.

Summarizing reports by effective working day exceeding 12 AM changes the behavior of reports from a 24 hour working day, to a working day wherein the encoder determines when a day starts and ends. The user is offered to start a new day every time the server is started and a new day is detected.



Server Tab

The server tab options tweaks the behavior and appearance of the server, including how the server is found via TCP/IP, how reports are viewed, how the mouse behaves, how the icons are displayed, etc...

The *Background Picture*, *Auto arrange list icons* and *Edit list icon position* settings are used layout a floor plan for the large icon view of the server. The icons in the main display representing client machines may be arranged in a custom arrangement to match their physical layout. Uncheck *auto arrange list*. To edit the arrangement, temporarily check the *editing position of items* setting and start arranging the icons on the main display. When done editing, uncheck the *editing position of items* setting.

The *Number of client computers shown* setting can be configured subject to restrictions of client license registration.

The *Select icon on mouse hover*, *Single click*, *Multiselect list items* and *Checkbox* settings determines


whether clicking on the server behaves like a button or like a multi select list.

Automatic data backup maintenance and *data backup folder* sets the auto data backup and recovery behavior of the server program. When set, the program copies the "Data.mdb" file to the data backup folder. 7 day backups are stored on the folder.

You may specify the system to email the *daily sales report* every n hours.

The shared public folder of the server also called the system path is a legacy communications channel between clients and server. It is required if you want to centralize configuration of ads rotation feature.

Do not change the *System folder*, *Disable web server*, *Simple communication mode*, *Persist client connection* and *Listen port* settings unless you know what you are doing



Client Tab


The client tab of the server options allows configuration for synchronizing the time with the server, sound warning on timeout on the clients, wallpapers, etc...

Chat options allow the attendant or the user to send messages to each other.

The *Log program usage* produces a report of what programs are being used on the client program. This setting determines how frequently the client program reports what program is the foreground

process on the client machine. However, change in the foreground program will immediately be reported to the server.

The wallpapers set the ads rotation feature of the clients. Here you can set if all the stations show the station number on the upper right hand corner of the screen, if ads configuration is centralized on the server and if the images are stretched to fit the size of the screen. If ads configuration is not centralized, it may be set from the client program main menu by keying in Shift+A and logging in as an administrator on the client. Properly configure the system path on the client via the options button. Click on the images button to set the pictures to be displayed by the ads feature. The format of the pictures may be gif, jpg or bmp.



Locking Tab

The locking tab specify how the client program locks on timeout.

Each program may be configured to lock by screen lock, mouse/keyboard lock, kill program upon timeout, shutdown or restart. Certain games may hang if the screen is locked upon timeout so mouse/keyboard lock is used (ex. half life, quake, diablo). These programs are called 'misbehaved programs'. In addition, mouse/keyboard lock may be converted into a kill program after a predefined number of seconds..

In addition, default to open time may be set if a per minute rate charging is required. Default to autotimeout if the client program should strictly lock when the reserved time is up.

When Norton Antivirus is available on the client machine, uncheck the *Force shutdown* setting

otherwise, windows will hang during shutdown.


Application restrictions enforces restrictions on the client windows environment.

Restrict non-internet rental accounts restricts access to applications defined to be internet programs for non-internet rental account timein.

Firewall allows you to closed certain ports for specific rental accounts, say you want to disable a specific online game for ordinary GAMING rental accounts.

Restrict unauthorized program execution restricts access to programs that do not have 'application shortcuts' or '.lnk' files on the client windows desktop folder including subfolders nested by one level.

Defaults allow you to specify whether autotimeout or opentime is the default on timein.



Security Tab

The security tab allows windows restrictions to be set such as hiding the start menu, control panel, desktop icons, drives, etc... The custom quick launch may be enabled since it cannot be configured by customers, thus being more secure than the default windows quick launch toolbar.

Security accounts may be defined. Attendants have access to the user menu of the server. Administrators have additional access to the admin menu of the server. Technicians have attendant

priveledges on the server and disable rights on the client.

Restrict editing for charged amount and pause/free minutes settings are applied on the timeout dialog of the server.

Desklock restrict access to the windows environment like control panel, run command, start menu, desktop, etc... Hide drives allows you to hide drives from the user.

Protect windows autostart registry and Terminate all programs on timeout are the antikeylogger settings that terminates all opened programs (except those with different locking definitions on the misbehaved programs list) during timeout on the client machine. The two settings work hand in hand to protect against keyloggers and porn sites that add themselves to the windows startup registry. You can check for these programs from the Admin menu - error report menu item. Upon timeout, processes/programs (which are killed) and the windows startup are cleaned up. To specify a different behavior for cleaning up processes, specify how you want to treat these programs from the misbehaved programs list option of the locking tab




Prepaid Tab

The prepaid tab allows prepaid ticket printing options to be set such as prepaid ticket header, row or column count for prepaid ticket report, prepaid types, etc...

'Remote member login' checkbox must be checked to allow users to login by themselves from the client side.

Group Accounts button allow you to create groups and default discounts for members of these groups

Prepaid Accounts define a prepaid type with a given price for a given prepaid value. For example you can define a new prepaid type, 'Prepaid100' that is sold for 100.00 for a prepaid value of 120.00.



The image shows a screenshot of the 'Options' dialog box, specifically the 'Prepaid' tab. The dialog has a title bar with a close button. Below the title bar is a row of icons for different settings: Rates, Server, Client, Locking, Security, and Prepaid (which is selected). The 'Prepaid' section contains several settings:

- Prepaid Ticket header:** A text field containing 'TICKET'.
- Number of Columns for Prepaid Ticket:** A numeric field set to '5'.
- Number of Rows for Prepaid Ticket:** A numeric field set to '12'.
- Auto send to printer for Prepaid Ticket Report:** A checked checkbox.
- Prepaid expires after N days:** A numeric field set to '0'.
- Auto delete empty prepaid:** A checked checkbox.

On the right side of the 'Prepaid' section, there are three buttons: 'Group Accounts', 'Member Accounts', and 'Prepaid Accounts'.

Below the 'Prepaid' section is a 'Miscellaneous' section with the following settings:

- Credit authorization password:** A text field.
- Default credit limit:** A numeric field set to '0'.
- Minimum adhoc load payment amount:** A numeric field set to '0'.
- Members / prepaid can login remotely:** A checked checkbox.
- Allow credit for members / prepaid:** An unchecked checkbox.
- Show logon form on mouse move:** A checked checkbox.

At the bottom of the dialog, there are six buttons: 'Reset', 'Factory', 'Wizard', 'Manual Start', 'Apply', and 'Close'.

Configuration Wizard

This dialog allow easy configuration of the most commonly used settings from the *Options dialog*.

Configuration Wizard

Rates

20.00 Gaming Rate Per Hour

30.00 Internet Rate Per Hour

0 Block Charging (minutes) ex. round by 15 min

0 Rounding grace period (minutes) ex. 2min

0 Round charged amount by

☐ Default to open time

☐ Default to autotimeout

Server

☒ Icons behave like button

☐ Icons behave like list (multiselect)

25 Number of clients stations to display
(30 available licenses)

Background Picture

☐ Auto arrange list icons

☐ Edit list icon position

Miscellaneous

☒ Norton Antivirus installed on client machine

☐ Wake on lan hardware available on client machine

Security

☐ Strict

☐ Moderate

☒ Relaxed

Admin Password

User Password

Email Reports

Email Addresses: Every Hour Interval(s)

0

Prepaid

TICKET Prepaid Ticket header

0 Prepaid expires after N days

☒ Do not show this dialog

Rental Rates and Rental Account

The *Rental Account* is the central point of management for access to the client station. It defines the security context as well as the rental rate for use of the machine during timein. As such, understanding the concept of the rental account is fundamental to using the program effectively.

Default Rate Definition

A default rate definition is provided for all rental accounts. These settings are used unless you override the particular setting under the definition of the rental account itself. The meaning of these rates settings are defined [here](#).

Options

Rates | Server | Client | Locking | Security | Prepaid

Duration

60 Default duration on manual timein (minutes)

0 Block Charging (minutes) ex. round by 15 min

0 Rounding grace period (minutes) ex. 2min

0 Minimum duration (minutes)

0 Default free minutes (minutes)

0 Maximum paused duration (minutes)

Charged Amount

0 Minimum charged amount

0 Round charged amount by

☐ Round up charged amount

Miscellaneous

☐ Working day exceeds 12 AM for sales reporting

☒ View reports as web page

Rental Accounts

Sales Accounts

Expense Accounts

Receipt Printing

PC Rate Differential

Reset Factory Wizard Manual Start Apply Close

Rental Account List

The rental account has the following sub sections for its definitions

- **Main** - These are the rates for the given rental account. Prices may be set for Per Hour, 45 Minute, 30 Minute, 15 Minute and 1 Minute Rate or instead just set the Per Hour Rate and the program will automatically divide it for each of the other rates. A password may also be set for access to this rental rate account.
- **Defaults** - These settings determine what is the default rental account suggested by the program during timein on both the server and the client program
- **Discounts** - These settings define discounts provided during off-peak hours
- **Duration** - These are the settings as those provided in the options dialog
- **Charged Amount** - These are the settings as those provided in the options dialog

Rental Account List										
Account	Per Hr	45 Min	Half Hr	15 Min	Per Min	Play...	Logon	Inter...	PayB...	Default
ERRORS	0	0	0	0	0	0	No	Yes	No	
FREETIME	0	0	0	0	0	0	No	Yes	No	
OWNER	0	0	0	0	0	0	No	Yes	No	
REPAIR	0	0	0	0	0	0	No	Yes	No	
GAMING	20	15	10	5	0	0	Yes	No	No	
RENTAL	20	15	10	5	0	0	No	No	No	Default
INTERNET	30	22.5	15	7.5	0	0	Yes	Yes	No	

Buttons: Add, Edit, Delete, Save, Close


In addition the following points need to be clarified

- The *Allow internet* setting work hand in hand with the *Restrict Internet* setting found in the *Locking Tab*.
- The *Pay All U Can* setting define a rate that is not based on length of duration the client is used.
- The *Pay Before Play* setting determine whether the charges are added by system to the sales record on timein or on timeout of the station.
- The *Allow Remote Logon* setting work hand in hand with the *Member/Prepaid can remotely login* setting found in the *Prepaid Tab*. This setting determines whether this rental account is available to the customer during remote login.


Edit Rates		
Main Rate Account: INTERNET Per Hour Rate: 30 45 Min Rate: 22.5 Half Hour Rate: 15 15 Minute Rate: 7.5 Per Minute Rate: 0 Password: Play all U Can: ☐ ☒ Allow Internet ☐ Pay Before Play ☒ Allow Remote Logon Run command on timein:	Defaults Default Duration: 0 Default Day: None Default Time From: Default Time To: ☐ Default Discounts Disc 1: Disc 2: Disc 3: Disc 4: Disc 5:	Duration Block Charging (minutes) ex.round by 15min Rounding grace period (minutes) ex.2min Minimum duration (minutes) Default free minutes (minutes) ☐ Open Time ☐ Autotimeout Charged Amount Minimum charged amount Round charged amount by
OK Cancel		

PC Rate Differential

This list define an adjustment to the rental rate defined for a particular station. The adjustment may be positive or negative as well as an exact amount or a percentage.



The 'PC Price Adjustment List' window displays a table with the following headers: PC No., Description, Amount, Percent, and Per Hour. The table is currently empty. Below the table, there are five buttons: Add, Edit, Delete, Save, and Close.




The 'Add PC Price Adjustment' window contains a 'Main' section with the following fields:

- PC Number:
- Adjust Amount (+incr/-decr):
- Adjustment Percent:
- Adjustment Per Hour:
- Description:

At the bottom, there are 'OK' and 'Cancel' buttons.

Member Group

This list define discounts to the rental rate given to members of the defined group.




The 'Add Member Group' window contains a 'Main' section with the following fields:

- Group Name:
- Rental Disc Amount:
- Rental Disc Percent:
- Rental Disc Per Hour:
- Description:

At the bottom, there are 'OK' and 'Cancel' buttons. A 'Close' button is also visible on the right side of the window.

Prepaid Type

This list define the price and load value of each prepaid of a given type. The load value deducted during use of the client machine is defined by the rental rate of the selected rental account for the particular station.




Locking and Security


The settings under the *Locking Tab* and the *Security Tab* of the Options dialog define how the client program locks on timeout and how the application restricts access to features of the windows environment respectively

Application Restrictions

The three settings under the *Locking Tab* are activated for *Strict Security* setting and are disabled for *Moderate Security* and *Relaxed Security* settings of the *Configuration Wizard* dialog.




The *Restrict non-internet rental account* setting would block access to the programs on the list when you timein the station under a non-internet enabled rental account. As such, you can control if the user is able to access the internet or not.



The *Restrict firewallled ports* setting would block a list of defined port based on the rental account you timein the station. For example you could block the port for game servers for all rental accounts except the GAMING rental account.


Some well known ports are listed below

- Battlenet ----- 4000, 6112 - 6119
- Yahoo Games ----- 11999
- Network ----- 445, 135 - 139
- Web Browsing ----- 80, 8080, 8001, 443
- FTP ----- 21
- Ragnarok ----- 5000, 5112, 6900
- Warcraft ----- 6112 - 6119




The *Restrict unauthorized program execution* setting would block access to programs on the client machine. These programs are blocked by the windows operating system itself so there is no way to bypass this restriction. To allow execution of certain programs like MS Word, Diablo, Counterstrike, Notepad, Internet Explorer and the like, you add 'Application Shortcuts' or .Lnk files to 1.) the

windows desktop of the client machine or 2.) a folder on the windows desktop.




Locking behavior is defined for *Normal Program Locking* and *Misbehaved Program Locking* that determine how the client machine is locked on timeout


Each program may be configured to lock by screen lock, mouse/keyboard lock, kill program upon timeout, shutdown or restart. Certain games may hang if the screen is locked upon timeout so mouse/keyboard lock is used (ex. half life, quake, diablo). These programs are called 'misbehaved programs'. In addition, mouse/keyboard lock may be converted into a kill program after a predefined number of seconds.




The *Security Tab* of the *Options dialog* define windows restrictions that restrict access to parts of the windows shell environment. This includes drives, control panel, start menu, desktop, etc...



Separate desklock settings are provided for the client machine and the server machine.




The Security Tab has *Protect windows autostart registry* and *Terminate all programs on timeout* which are the antikeylogger settings that terminates all opened programs (except those with different locking definitions on the misbehaved programs list) during timeout on the client machine. The two settings work hand in hand to protect against keyloggers and porn sites that add themselves to the windows startup registry. You can check for these programs from the Admin menu - error report menu item. Upon timeout, processes/programs (which are killed) and the windows startup are cleaned up. To specify a different behavior for cleaning up processes, specify how you want to treat these programs from the misbehaved programs list option of the locking tab



When you click the *Users* button in the *Security Tab* the *Security User List* dialog is displayed. The users in this list may be Administrators, Attendants and Technicians. The privileges of these users is defined as follows:

- Administrator - Admin Menu, User Menu and Automatic Disable on Technician Logon on the Client, Disable on Admin Logon on the Client
- Technician - User Menu and Automatic Disable on Technician Logon on the Client
- Attendant - User Menu

Technician logon is available for all 3 levels when the *Users can login remotely* setting is enabled and a *Rental Account* is defined in the User List dialog.



Troubleshooting

Common problems that may be encountered include the following:

1. The client is not responding to timein/timeout on the server.

The server is issuing commands to the client by communicating through the TCP/IP network. Something could be wrong on any or all of the following: 1) The network card is not functioning properly. 2) The network adaptor is not functioning properly. 3) The network protocols are not properly configured. 4) The server IP address has not been fixed. 5) The listen port of the server option is not set at 2556. 6) The server port on the client is not set at 2556. 7) The server IP address is not properly set on the client.

2. I want to disable the client agent so that it does not lock.

The client locks windows unless the server times it in. To temporarily remove this lock, you must disable the client agent. To do this from the server, login with an admin account (user 'admin', password 'supervisor'), then select the station number on the list you want to disable. Afterwards, select the admin menu and choose disable. Or choose disable all to disable all machines. On the client you may disable the client agent from the main menu or through the Shift+Z key combination. Again, you will be required to logon with an administrator password. To return the client agent, all you will need to do is to launch the client agent program from the windows start menu.

3. Are there any compatibility issues with certain games?

Yes. Counterstrike, Diablo and Quake may cause windows to hang when you accidentally press the Start Button keyboard button on an extended windows keyboard, or when you minimize Counterstrike with the Alt+Tab key combination. The same problem may occur when you timeout the client machine from the server. The sentinel server has a "Misbehaved Programs List" on the admin menu. These are the programs that react like this when the windows start button is pressed.

The client agent responds differently to these programs when it tries to lock, it terminates these programs or it disables the mouse and keyboard depending on the setting on the client options form.

4. Why has the windows start menu and desktop icons disappeared?

This is normal. It is set from the server options form. You may disable desklock for either the client or the server when ever the program starts. You may manually set desklock at any time from the server admin menu or from the client main menu.

5. Why has the settings on the server not taken effect on the client?

The settings on the server is automatically detected by the client every time the program starts. You will have to restart the client for the server setting to take effect. Moreover, there may be a network connection problem between the server and the client.

6. Why is the report not displaying properly?

If internet explorer is not properly configured, the report may not display. To solve this problem, double click on the internet explorer icon and configure.

7. Why is the report not being emailed to the address i configured?

If outlook express is not properly configured, the report may not email. To solve this problem, double click on the outlook express icon and configure. You may also set the email program to 'warn me when other applications try to send mail as me' setting to false from the *Options dialog, Security Tab*.