DELFT UNIVERSITY OF TECHNOLOGY

MASTER THESIS

MASTER THESIS

Author: Serwan Asaad

Supervisor: Dr. Alessandro Bruno

May 16, 2015

Contents

I	Deep-reactive ion etched resonators	3
II	Muxmon experiment	5
1	Muxmon chip architecture	8
2	Qubit characterization	10
	2.1 Part I: Continuous-wave measurements	10
	2.1.1 Scanning for resonators	11
	2.1.2 Powersweeping the resonators	11
	2.1.3 Scan for qubit sweet-spots	12
	2.1.4 Scanning for qubits	14
	2.1.4.1 Avoided crossing	14
	2.1.4.2 Spectroscopy	15
	2.2 Part II: Time-domain measurements	15
3	Calibration routines	16
4	Randomized benchmarking	17
Аp	ppendices	18
A	Additional notes	19
	A.1 Qubit characterization	19
	A.1.1 Part I: Continuous-wave measurements	
	A.1.1.1 Powersweep	19
	A.1.1.2 Spectroscopy	19
В	O Company of the comp	20
	B.1 Tracked spectroscopy	20
	B.2 Peak finding	20
	B.3 Compiled RB?	20

Introduction

Part I Deep-reactive ion etched resonators

TODO:

- Explain heterodyne detection
- Explain VNA
- ullet Explain that resonance frequency $f_{\rm r}$ is not necessarily at the transmission minimum when the resonator exhibits asymmetry.

Part II Muxmon experiment

TODO: Explain surface code architecture

Introduction

At this moment circuit QED is at the stage where multi-qubit experiments are being realized.

Chapter 1

Muxmon chip architecture

Topics that should be explained in this section:

- The Muxmon0 and Muxmon1 chip are designed with two purposes
 - Testing multiplexing using the Duplexer
 - 2. Explore qubit frequency re-use
- Explain similarities of chips
 - Three qubits per chip
 - All three qubits have individual flux tuning
 - Air bridges are used, not only for connect the ground planes, but also such that the feed line can pass over other coplanar waveguides without contact
- Explain differences between Muxmon0 and Muxmon1.
 - The Muxmon0 chip has a driving line connected to each of the qubits.
 It has two resonator buses at 4.9 GHz and 5.0 GHz.

These could also be used for two-qubit gates.

Advantage Able to fully control each qubit individually, even when multiple qubits share the same frequency.

Advantage Less coupling between data qubits.

Disadvantage Requires more driving lines.

Disadvantage Adds extra source of dissipation for the qubits.

 The Muxmon1 chip has two driving lines, each capacitively coupled to one of the two data qubits, and to the ancilla qubit.

Advantage Less driving lines required

Advantage Less dissipation due to capacitive coupling

Disadvantage Cannot individually control data qubit and ancilla qubit when they share the same frequency

Disadvantage More coupling between qubits

- Simplified model of the surface code
- Explain concepts of cross-coupling and readout cross-talk

Cross-coupling The coupling between qubits.

Cross-coupling leads to transfer of excitation.

An associated coupling strength **g** can be associated to cross-coupling.

Can be determined by driving one qubit extremely hard, and measuring signal from other qubit.

TODO: Show values of cross-coupling found, or do this in characterization section **TODO:** Leads to coherent errors?

TODO: Two types of cross-coupling? Direct leakage of pulse pulse, and transfer of excitation? cross-driving?

Readout cross-talk Coupling between a qubit and a resonator that are not directly coupled.

A part of the signal measured from one resonator is then due to the state of another qubit

TODO: Understand more behind readout cross-talk

Left to think about:

- Should I already include items such as coherence times, the fact that Muxmon0 performs better than Muxmon 1?
- Where should I include coherence times versus frequency?
- Should the part on cross-coupling and readout cross-talk not be in characterization section?
- Should the section on the Duplexer go in here?

Figures that need to be included:

- Muxmon0 and Muxmon1 chip, preferably optical microscopy
- SEM image of air-bridges such that coplanar wave-guides cross without intersecting
- schematic of cross-coupling and readout cross-talk
 It could be good to create this using the actual Muxmon chip as background, with arrows indicating how the different effects operate

Chapter 2

Qubit characterization

Description This chapter gives a step-by-step description of how to find a resonator and qubit, and subsequently how to tune the qubit's parameters.

In the design of cQED chips, the parameters of the qubits and resonators are always targeted which are ideal for the experiment. For coplanar waveguide resonators one can already obtain relatively good parameters for the required dimensions from simple formulae **TODO:** refer to formula. For superconducting transmon qubits, however, finding the right dimensions that correspond to the desired parameters is a much more complicated process. The qubit's frequency, for instance, depends on the qubit's coupling energy E_c and Josephson energy E_J . The coupling energy E_c can be reasonably estimated from classical simulations. Finding the right dimensions for the Josephson junction that result in the desired Josephson energy E_J , however, is difficult, and usually physically testing different junctions is necessary to determine an accurate conversion from the desired E_J to the Josephson junction dimensions.

Nevertheless, the actual parameters of the resonators and qubits are almost never where one expects them to be. Once the sample is cooled in the dilution refrigerator, an inevitable game of hide-and-seek follows with the goal of finding the frequency of the resonators and qubits, and subsequently determining their properties. This chapter describes the measurements that were performed to characterize the MuxMon samples.

2.1 Part I: Continuous-wave measurements

Once a sample is properly cooled down it is ready to be measured. At this stage the sample is still an unknown terrain, where the experimenter only has a rough map, containing the sample's targeted parameters, and the specific properties of the resonators and qubits.

The first step is to look for signs of life. These manifest themselves as resonance frequencies of the resonators and the qubits that are coupled to them. As we are not yet interested in the properties of the resonators and qubits which can only be obtained through measurements with accurately timed pulses, we send continuous tones through the feedline, and measure deviations in the transmission. These measurements are known as continuous-wave measurements

2.1.1 Scanning for resonators

Since communication with the qubits is mediated through their coupling to resonators, the first step is to find these resonators. This is done using a transmission measurement, in combination with heterodyne detection, and has been explained in section **TODO:** Create section in Resonator chapter.

There is one difference in measuring a resonator when there is a qubit coupled to it. In this case the resonance frequency of the resonator, which henceforth shall be known as the resonator's frequency f_r , is shifted from its bare resonance frequency f_{bare} (its frequency in the absence of a coupled qubit). The amount by which f_r is shifted from f_{bare} depends on how much the ground to excited state transition frequency of the qubit, which shall be mentioned as the qubit's frequency f_q , differs from the resonator's bare frequency f_{bare} . This difference is known as the detuning $\Delta = f_{\text{qub}} - f_{\text{bare}}$.

 2χ the resonance frequency of the qubit's ground to excited state transition, which henceforth shall be denoted as the qubit's frequency f_q

There is one additional constraint on transmission measurements in the case where a resonator is coupled to a qubit.

TODO:

- Explain why using a high power is good.
- Explain that the quality factor is low because the resonator is coupled strongly to the qubit (equation including coupling to qubit?)

Figures:

• Figure of transmission showing all three Muxmon0 resonators

2.1.2 Powersweeping the resonators

Once the resonators have been located, the next stage is to find the qubit that is capacitively coupled to each of the resonators. Instead of directly scanning the entire frequency spectrum in search of the qubit, it is relatively straightforward to perform some initial measurements aimed at gaining information about our resonator and qubit, which will allow us to search for our qubit with much greater accuracy.

The capacitive coupling between the resonator and qubit results in a shift of the resonator frequency dependent on the state of the qubit. This shift disappears when the resonator is driven with sufficient power, in which case its resonance frequency shifts to the bare cavity frequency f_{bare} . If this frequency shift is observed, it indicates that the qubit is alive. Measuring this frequency shift is commonly done in a powersweep. A powersweep is a measurement in which a resonator scan is performed for a range of powers.

A powersweep additionally provides information about at what power the resonator enters the **TODO:** nonlinear? regime. For measurements involving the qubit the readout power must be below this threshold power. Furthermore, from the frequency shift between the dressed cavity frequency and the bare cavity frequency, it is possible to estimate the

amount of detuning between the qubit and the resonator. This is done through the relation: **TODO:** insert relation

If no shift is observed, it could mean that the qubit is dead (e.g. because the Josephson junction is shorted). However, this is not necessarily the case. An alternative possibility is that the resonance frequency of the qubit is sufficiently far away from that of the resonator, and as a result the frequency shift cannot be discerned. At this point it is too early to draw conclusions, and we may almost draw the analogy with Schrödinger's cat in a box.

TODO:

- Explain better theory behind dispersive shift 2χ
- Explain theory behind transition to bare cavity frequency
- Refer to thesis Reed for more info on frequency shifts

Figures:

Powersweep of ancilla qubit

2.1.3 Scan for qubit sweet-spots

Some of the qubits have a tunable resonance frequency. This is done through a superconducting quantum interference device (SQUID). In this case the two islands that compose the transmon qubit are connected by two Josephson junctions instead of one, effectively forming a loop. The SQUID loop is sensitive to the amount of flux passing through the loop. The amount of flux going through the SQUID loop can be changed by changing the surrounding magnetic field. This is commonly done by having a flux bias line in close proximity to the SQUID loop. Current flowing through the flux-bias line alters the magnetic field in the vicinity of the SQUID loop, and hence changes the amount of flux through the SQUID loop. A digital-to-analog converter is used to specify the amount of current that is sent through the flux bias line. Depending on the amount of flux through the SQUID loop, the resonance frequency of the qubit changes accordingly. these qubits are therefore called flux-tunable.

For qubits that are flux-tunable, finding the sweet-spot of the qubit can be done without knowledge of the qubit's frequency. This can be done by sweeping the DAC voltage and measuring the shift in the resonance frequency. Because the frequency of the qubit varies as the amount of current through the flux-bias line changes, the detuning between the qubit and the resonator consequently changes. As a result the resonator shift **TODO:** χ ? also varies. At the sweet-spot of the qubit, the resonator's frequency f_r is at a maximu,. This is irrespective of whether the qubit's frequency f_q is above or below the resonator's frequency.

The accurate way to measure the sweet-spot is to perform resonator scans as the DAC voltage is varied. The result is a 2D scan shown in **TODO:** Figure.

A faster second approach for finding the qubit sweet-spot, at the cost of providing less information, is by choosing a fixed frequency close to the resonator's frequency f_r (preferrably slightly below, where the transmission slope is steepest). By measuring the amount of transmission as the DAC voltage is being varied, one obtains essentially a line-cut of **TODO:**

Figure. The idea this measurement is that if the qubit's frequency f_q decreases, the resonator's frequency also decreases, resulting in a decrease in transmission (closer to f_r). Likewise, if the qubit's frequency f_q increases, the resonator's frequency increases **TODO:** Why?, resulting in an increase in transmission (further away from f_r).

At the qubit's sweet-spot, the resonator's frequency f_r is at a maximum, and so the transmission should also be at a maximum. Furthermore, because the amount of detuning only depends on the deviation from the flux sweet-spot **TODO:** improve, the transmission should be symmetric with respect to the DAC voltage sweet-spot. If the resonator's frequency f_r shifts by a large amount in the course of this measurement, it becomes harder to determine where the sweet-spot is (although even then often it can still be discerned). Nevertheless, this method is considerably faster than performing a full two-dimensional scan of frequency versus DAC voltage, and in most cases it works like a charm.

In the case where the powersweep showed no measurable frequency shift, these two measurements are also useful in discerning whether or not the qubit is actually dead, or whether it was simply far detuned from the resonator.

TODO:

- Explain avoided crossing?
- Explain how qubit's frequency has a cosine dependence on DAC
- Give detailed information on SQUID loop
 - Why does the qubit frequency change in a SQUID loop
 - Sweet-spot
- Mention flux-noise?
 - 1/f noise
 - usually not limiting, as it is very slow
 - This noise can be seen as occasional jumps (every few hours?) It would mean that every few hours the frequency must be recalibrated.

Figures:

- SEM picture of SQUID loop, including flux-bias line
- Figure of 2D resonator scan vs DAC voltage
- Figure of 1D resonator fixed frequency DAC voltage scan

2.1.4 Scanning for qubits

Once the preliminary measurements have been performed that characterize the resonators and provide hints about the whereabouts of the qubit it is time to actually find its frequency.

The measurement to perform in order to find the qubit depends on the amount of detuning between the resonator and qubit, which can be estimated from powersweep measurements. If the amount of detuning is small ($<\sim 100\,\mathrm{MHz}$), the frequencies of the qubit and resonator are close to the avoided crossing, resulting in a strong coupling between the two. In this case the qubit can be seen in a simple transmission measurement. If the detuning between the resonator and qubit is sufficiently large ($>\sim 100\,\mathrm{MHz}$), the qubit can be found using two-tone spectroscopy

2.1.4.1 Avoided crossing

When the qubit's frequency is close to that of the resonator, the two experience a strong coupling **TODO:** Why?

Avoided crossing info:

- Actually the threshold is determined by the ratio between detuning and coupling strength
- The coupling strength *g* is the minimum distance between the splitting
- From Reed's thesis p.63 explanation of this avoided crossing is given

$$E_0 = -\frac{\hbar\Delta}{2} \tag{2.1}$$

$$E_1 = n\hbar\omega_r \pm \frac{\hbar}{2}\sqrt{4g^2n + \Delta^2}$$
 (2.2)

Joining $E_0 + E_1$ results in a qubit approaching a resonator from the top. When the frequency of the qubit equals that of the resonator, the energy difference reaches a minimum, and is equal to 2g.

TODO:

- Explain the quton fobit behaviour near the avoided crossing
- Explain how one can extract coupling from avoided crossing

figures:

· Figure of avoided crossing

2.1.4.2 Spectroscopy

An increase in the detuning between the resonator and qubit is accompanied by a . Therefore, when driving at the qubit's frequency, the deviation in the transmission becomes less, and at a certain amount of detuning it is not measurable anymore.

Explain in this Spectroscopy section:

•

If the qubit is flux-tunable, one important question to ask is: at what DAC voltage should the qubit be searched?

There are several options. The first option is to choose zero DAC voltage. In most cases this is alright, but there are cases when this is a bad choice. For instance, due to trapped magnetic fields during cool-down the qubit could be positioned at the anti-sweet-spot for zero DAC voltage, in which case finding the qubit will be next to impossible.

A better option is to choose a DAC voltage depending on the amount of detuning previously measured. Ideally either a few hundred megahertz or zero.

TODO:

- Use relatively high source power, results in power broadening
- Mention what to do if qubit is close to or far away from resonator
- Mention the term transmission measurement earlier on.

2.2 PART II: TIME-DOMAIN MEASUREMENTS

Page 15 of 20

Chapter 3

Calibration routines

Chapter 4

Randomized benchmarking

Appendices

Appendix A

Additional notes

A.1 QUBIT CHARACTERIZATION

A.1.1 Part I: Continuous-wave measurements

A.1.1.1 Powersweep

• If the resonator seems to disappear after the transition from dressed frequency to bare frequency (or vice versa), this is likely due to the qubit being extremely close to the resonator, and so the frequency shift is large.

A.1.1.2 Spectroscopy

• If the deviation in transmission becomes less due to more detuning, increasing the power can also increase the contrast.

Appendix B

Algorithms

- **B.1** TRACKED SPECTROSCOPY
- **B.2** PEAK FINDING
- **B.3** COMPILED RB?