

# **Packet Tracer - Troubleshoot Connectivity Issues**

### **Addressing Table**

Device	Interface	IP Address	Subnet Mask	Default Gateway
R1	G0/0	172.16.1.1	255.255.255.0	N/A
	G0/1	172.16.2.1	255.255.255.0	N/A
	S0/0/0	209.165.200.226	255.255.255.252	N/A
R2	G0/0	209.165.201.1	255.255.255.224	N/A
	S0/0/0 (DCE)	209.165.200.225	255.255.255.252	N/A
PC-01	NIC	172.16.1.3	255.255.255.0	172.16.1.1
PC-02	NIC	172.16.1.4	255.255.255.0	172.16.1.1
PC-A	NIC	172.16.2.3	255.255.255.0	172.16.2.1
РС-В	NIC	172.16.2.4	255.255.255.0	172.16.2.1
Web	NIC	209.165.201.2	255.255.255.224	209.165.201.1
DNS1	NIC	209.165.201.3	255.255.255.224	209.165.201.1
DNS2	NIC	209.165.201.4	255.255.255.224	209.165.201.1

# **Objectives**

In this Packet Tracer activity, you will troubleshoot and resolve connectivity issues, if possible. Otherwise, the issues should be clearly documented so they can be escalated.

# Background / Scenario

Users are reporting that they cannot access the web server, www.cisco.pka after a recent upgrade that included adding a second DNS server. You must determine the cause and attempt to resolve the issues for the users. Clearly document the issues and any solution(s). You do not have access to the devices in the cloud or the server www.cisco.pka. Escalate the problem if necessary.

**Note:** Router R1 can only be accessed using SSH with the username **Admin01** and password **cisco12345**. Router R2 is in the ISP cloud and is not accessible by you.

#### Instructions

### Step 1: Determine connectivity issues from PC-01.

- a. On PC-01, open the command prompt. Enter the command **ipconfig** to verify what IP address and default gateway have been assigned to PC-01. Correct as necessary according to the Addressing Table.
- b. After verifying/correcting the IP addressing issues on PC-01, issue pings to the default gateway, web server, and other PCs. Were the pings successful? Record the results.

Ping to default gateway (172.16.1.1)? Yes

```
To web server (209.165.201.2)? Yes

Ping to PC-02? Yes

To PC-A? No

To PC-B? No
```

c. Use the web browser to access the web server on PC-01. Access the web server by first entering the URL http://www.cisco.pka and then by using the IP address 209.165.201.2. Record the results.

```
Can PC-01 access www.cisco.pka? Yes
```

Using the web server IP address?

d. Document the issues and provide the solution(s). Correct the issues if possible.

PC-A and PC-B is not reachable. No problem in PC-01 and also the port of the router. There is a problem of the IP address of PC-01 and solved.

## Step 2: Determine connectivity issues from PC-02.

- a. On PC-02, open the command prompt. Enter the command **ipconfig** to verify the configuration for the IP address and default gateway. Correct as necessary.
- b. After verifying/correcting the IP addressing issues on PC-02, issue pings to the default gateway, web server, and other PCs. Were the pings successful? Record the results.

Ping to default gateway (172.16.1.1)? Yes

To web server (209.165.201.2)? Yes

Ping to PC-01? Yes

To PC-A? No

To PC-B? No

c. Navigate to www.cisco.pka using the web browser on PC-02. Record the results.

Questions:

Can PC-02 access www.cisco.pka? Yes

Using the web server IP address?

d. Document the issues and provide the solution(s). Correct the issues if possible.

PC-A and PC-B can not be pinged and the gate way of the PC-02 is not correct. Solved.

### Step 3: Determine connectivity issues from PC-A.

- a. On PC-A, open the command prompt. Enter the command **ipconfig** to verify the configuration for the IP address and default gateway. Correct as necessary.
- b. After correcting the IP addressing issues on PC-A, issue the pings to the web server, default gateway, and other PCs. Were the pings successful? Record the results.

To web server (209.165.201.2)? No

Ping to default gateway (172.16.2.1)?

Ping to PC-B? Yes

To PC-01? No

To PC-02? No

c. Navigate to www.cisco.pka using the web browser on PC-A. Record the results.

Can PC-A access www.cisco.pka?

No, Host Name Unresolved

Using the web server IP address?

No. Request Timeout

d. Document the issues and provide the solution(s). Correct the issues if possible.

Default gate is not ping properly and the router R1 port not 0/1 IP address is not correct. The problem is solve by changing the port IP address of the router

### Step 4: Determine connectivity issues from PC-B.

- a. On PC-B, open the command prompt. Enter the command **ipconfig** to verify the configuration for the IP address and default gateway. Correct as necessary.
- b. After correcting the IP addressing issues on PC-B, issue the pings to the web server, default gateway, and other PCs. Were the pings successful? Record the results.

To web server (209.165.201.2)? Yes

Ping to default gateway (172.16.2.1)? Yes

Yes Ping to PC-A? To PC-01? Yes To PC-02? Yes

c. Navigate to www.cisco.pka using the web browser. Record the results.

Can PC-B access www.cisco.pka? No

Using the web server IP address

Yes

d. Document the issues and provide the solution(s). Correct the issues if possible.

The issue is for PC-B navigation to website is not working but using the web server IP address it's working

e. Could all the issues be resolved on PC-B and still make use of DNS2? If not, what would you need to do? No, it's not possible but a temporary solution is to change ta DNS2 location to DNS 1.

#### Verify connectivity. Step 5:

Verify that all the PCs can access the web server www.cisco.pka.

Your completion percentage should be 100%. If not, verify that the IP configuration information is correct on all devices and that it matches what is shown in the addressing table.

Yes all are verified