

LAB 3- Create Table in the Database

A. Create Table

1. In database **propertyManagement**, the SQL CREATE TABLE statement is used to create a new table.
2. The basic syntax of the CREATE TABLE statement is as follows:

```
CREATE TABLE table_name(  
    column1 datatype,  
    column2 datatype,  
    column3 datatype,  
    .....  
    columnN datatype,  
    PRIMARY KEY( one or more columns )  
)
```


3. Below are the tables that should be created in database **propertyManagement**:

Tables:

- i. Cawangan (**cawno**, **jalan**, **bandar poskod**)
- ii. Pekerja
- iii. HartaUSewa
- iv. Pelanggan

4. SQL for creating table Cawangan

```
SQL> CREATE TABLE Cawangan(  
    cawno INT NOT NULL,  
    jalan VARCHAR (20),  
    bandar VARCHAR (25),  
    poskod INT,  
    PRIMARY KEY (cawno))
```




B. Alter Table

1. The ALTER TABLE statement is used to add, delete, or modify columns in an existing table.
2. The ALTER TABLE statement is also used to add and drop various constraints on an existing table.
3. The basic syntax of an ALTER TABLE command as follows.

```
ALTER TABLE table_name  
ADD column_name datatype;
```

4. Example for ADD a New Column to cawangan:



5. After successful add a new column, click structure. This will display all the column created.

Table structure

Relation view

	#	Name	Type	Collation	Attributes	Null	Default	Comments	Extra	Action
☐	1	cawno 	int(5)			No	None			 Change  Drop More
☐	2	jalan	varchar(20)	utf8mb4_general_ci		Yes	NULL			 Change  Drop More
☐	3	bandar	varchar(25)	utf8mb4_general_ci		Yes	NULL			 Change  Drop More
☐	4	poskod	int(11)			Yes	NULL			 Change  Drop More
☐	5	negeri	varchar(15)	utf8mb4_general_ci		No	None			 Change  Drop More


C. Modify Column

1. To change the data type of a column in a table, use the following syntax:

```
ALTER TABLE table_name  
MODIFY COLUMN column_name datatype
```

2. Example for MODIFY Column as below:

```
ALTER TABLE cawangan  
MODIFY negeri varchar(100);
```



3. After successful modify a column, click structure to show modified column.

The screenshot shows the 'Table structure' view of a table. The table has the following columns:

#	Name	Type	Collation	Attributes	Null	Default	Comments	Ext
1	cawno	int(5)			No	None		
2	jalan	varchar(20)	utf8mb4_general_ci		Yes	NULL		
3	bandar	varchar(25)	utf8mb4_general_ci		Yes	NULL		
4	poskod	int(11)			Yes	NULL		
5	negeri	varchar(100)	utf8mb4_general_ci		Yes	NULL		


D. Drop Column

1. To delete a column in a table, use the following syntax:

```
ALTER TABLE table_name  
DROP COLUMN column_name;
```

2. Example for DROP Column as below:

```
ALTER TABLE cawangan  
DROP COLUMN negeri
```



3. After successful drop a column, click structure.

E. DROP TABLE

1. The DROP TABLE statement is used to drop an existing table in a database.
2. To DROP a table, use the following syntax:

`DROP TABLE table_name;`

3. Example for DROP Column as below:

`DROP TABLE cawangan1`

F. INSERT DATA/RECORD into TABLE Cawangan

1. There are two syntax options for inserting data into a table.
2. Option 1:

Specify both the column names and the values to be inserted:

`INSERT INTO table_name (column1, column2, column3,...)
VALUES (value1, value2, value3, ...);`

3. Option 2:

`INSERT INTO table_name
VALUES (value1, value2, value3, ...);`

**If you are adding values for all the columns of the table, you do not need to specify the column names in the SQL query. However, make sure the order of the values is in the same order as the columns in the table.

Task: Insert the data below into the Table Cawangan

cawno	jalan	bandar	poskod
B005	5 Jalan Utara	Alor Star	50000
B007	Jalan Selatan 7	Seremban	70000
B003	Jalan Lingkaran 3	Besut	30000
B004	4 Jalan Utama	Kuala Nerus	40000
B002	Jalan Pinggiran 2	Johor Bahru	20000

Data cannot be inserted?? WHY?

**** CHECK datatype for cawno.**

**** need to MODIFY the datatype**