FreeBSD 9 Installation

bsdinstall

bsdinstall (FreeBSD 9) – (1)

```
=Welcome to FreeBSD=
                                            yo`:
 1. Boot [ENTER]
 2. [Esclape to loader prompt
 3. Reboot
 Options:
 4. [A]CPI Support: Enabled
 5. Boot Safe [Mlode: NO
 6. Boot [Slingle User: NO
 7. Boot [Vlerbose: NO
Autoboot in 8 seconds. [Space] to pause
```

□ http://www.freebsd.org/doc/handbook/bsdinstall.html


bsdinstall (FreeBSD 9) – (2)

☐ Install · Shell · Live CD



bsdinstall (FreeBSD 9) – (3)

☐ Setting hostname



bsdinstall (FreeBSD 9) – (4)

☐ Selecting components to install

```
FreeBSD Installer
                         --Distribution Select--
              Choose optional system components to install:
                [ ] doc
                           Additional documentation
                [*] games Games (fortune, etc.)
                           32-bit compatibility libraries
                [*] ports Ports tree
                           System source code
                 [ ] src
```

bsdinstall (FreeBSD 9) – (5)


- ☐ Partitioning methods
 - Shell gpart(8) \(\cdot \text{fdisk}(8) \(\cdot \text{bsdlabel}(8) \)



bsdinstall (FreeBSD 9) – (6)

☐ Guided Partitioning

- Select disk
- Replace { ad | da } by ada
- { ad | da } 's are linked to ada's



- How to partition the disk
 - > Entire Disk
 - ➤ Partition use free space



bsdinstall (FreeBSD 9) – (7)

☐ Guided Partitioning result

```
FreeBSD Installer
                  ----Partition Editor---
           Please review the disk setup. When complete, press
           the Finish button.
                         12 GB
                                   GPT
           ada0
             ada0p1
                         64 kB
                                   freebsd-boot
             ada0p2
                         11 GB
                                   freebsd-ufs
             ada0p3
                        627 MB
                                   freebsd-swap
                                                  none
          <Create> <Delete> <Modify> <Revert> < Auto > <Finish> |
Add a new partition
```

bsdinstall (FreeBSD 9) – (8)

☐ Manual Partitioning

```
FreeBSD Installer
                           --Partition Editor-----
            Create partitions for FreeBSD. No changes will be
            made until you select Finish.
           ada0
                          12 GB
           <Create> <Delete> <Modify> <Revert> < Auto > <Finish>
Add a new partition
```

bsdinstall (FreeBSD 9) – (9)

- ☐ Choose a partitioning scheme
 - GPT · MBR
 - DON'T use BSD!!!




bsdinstall (FreeBSD 9) – (10)

- ☐ Add partitions
 - freebsd-boot
 - > FreeBSD boot code. This partition must be first on the disk.

bsdinstall (FreeBSD 9) – (11)

☐ Final confirmation



bsdinstall (FreeBSD 9) – (12)


☐ Fetching → Checksum Verification → Extraction



bsdinstall (FreeBSD 9) – (13)

☐ Post-installation

- root password
- Network interfaces
 - ➤ Wired Static IPv4 / DHCP / Static IPv6 / SLAAC
 - > Wireless
 - > DNS
- Time Zone
- Services
- Add users



bsdinstall (FreeBSD 9) – (14)

☐ Final configuration

