
Linku per ta bere download XAMPP:


[XAMPP Download Link]

Instalimi i XAMPP:


1. **Zgjedhni instalimin duke iu pershtatur OS (Operation System) qe ju keni:**




2. **Hapeni XAMPP Setup qe eshte bere download nga hapi paraprak dhe klikoni next:**




3. Selektoni te gjitha komponentet si me poshte dhe klikoni next:




4. **Selektoni nje folder ku deshironi ta ruani XAMPP Server dhe klikoni next:**




5. **Klikoni next:**




6. **Klikoni next:**



7. **Prisni deri sa XAMPP te instalohet dhe klikoni next:**




8. **Zgjedhni nese deshironi te startoni Control Panel te XAMPP ose jo dhe klikoni Finish:**



9. **Zgjedhni gjuhen dhe klikoni Save:**




Pas instalimit hapeni Control Panel te XAMPP e cila do te duket si me poshte:




Ndryshimi i Portit (eshte opsional)

Per te ndryshuar portin e APACHE Server ndaleni serverin dhe klikoni ne butonin Config:



Zgjedhni opsionin e pare:



Navigoni deri te pjesa si me poshte:

```
#
# Listen: Allows you to bind Apache to specific IP addresses and/or
# ports, instead of the default. See also the <VirtualHost>
# directive.
#
# Change this to Listen on specific IP addresses as shown below to
# prevent Apache from glomming onto all bound IP addresses.
#
#Listen 12.34.56.78:8018
Listen 8018


#
# Dynamic Shared Object (DSO) Support
#
# To be able to use the functionality of a module which was built as a DSO you
# have to place corresponding `LoadModule' lines at this location so the
# directives contained in it are actually available _before_ they are used.
# Statically compiled modules (those listed by `httpd -l') do not need
# to be loaded here.
#
# Example:
# LoadModule foo_module modules/mod_foo.so
#
```

Ndryshoni portin ashtu sic ju deshironi:


```
#
# Listen: Allows you to bind Apache to specific IP addresses and/or
# ports, instead of the default. See also the <VirtualHost>
# directive.
#
# Change this to Listen on specific IP addresses as shown below to
# prevent Apache from glomming onto all bound IP addresses.
#
#Listen 12.34.56.78:8008
Listen 8008


#
# Dynamic Shared Object (DSO) Support
#
# To be able to use the functionality of a module which was built as a DSO you
# have to place corresponding `LoadModule' lines at this location so the
# directives contained in it are actually available _before_ they are used.
# Statically compiled modules (those listed by `httpd -l') do not need
# to be loaded here.
#
# Example:
# LoadModule foo_module modules/mod_foo.so
#
```

Startoni Apache Server dhe mund ta shihni qe tani porti ne te cilin ka startuar eshte 8008:




Startoni Apache Server dhe ne browser shenoni localhost:porti/dashboard ex. localhost:8080/dashboard, do te hapet faqja si me poshte ku mund te shihni versionin e PHP qe e keni te instaluar ne pajisjen tuaj.






Shenoni ne browser pjesen si me poshte dhe zgjedhni linkun si ne foto:



Zgjedhni opsionin si me poshte:



Previous releases
See also

Download

Microsoft Drivers 5.9 for PHP for SQL Server is the latest general availability (GA) version.

Download Microsoft Drivers for PHP for SQL Server (Windows)
GitHub Release Tag v5.9.0 (Linux and macOS packages are available here)

Version information

- Release number: 5.9.0
- Released: January 29, 2021

If you have feedback, the best way to contact the Microsoft Drivers for PHP for SQL Server team is by filing an issue on the GitHub repository.

Varesisht prej Sistemit Operativ zgjedhni opsionet e meposhtme:

Survey

Let us know how we are doing and how you use our drivers by taking our pulse survey:

Survey

Install


- On Linux and macOS run the commands below:
  ```
  sudo pecl install sqlsrv-5.9.0
  sudo pecl install pdo_sqlsrv-5.9.0
  ```
- To download Windows DLLs for PHP 7.3 or above from the PECL repository, please navigate to SQLSRV or PDO_SQLSRV.

▾ Assets 44


Zgjedhni Thread Safe varesisht prej versionit te PHP dhe Sistemit Operativ qe ju keni:

DLL List	
PHP 8.0	8.0 Non Thread Safe (NTS) x64 8.0 Thread Safe (TS) x64 8.0 Non Thread Safe (NTS) x86 8.0 Thread Safe (TS) x86
PHP 7.4	7.4 Non Thread Safe (NTS) x64 7.4 Thread Safe (TS) x64 7.4 Non Thread Safe (NTS) x86 7.4 Thread Safe (TS) x86
PHP 7.3	7.3 Non Thread Safe (NTS) x64 7.3 Thread Safe (TS) x64 7.3 Non Thread Safe (NTS) x86 7.3 Thread Safe (TS) x86


Hapeni XAMPP dhe klikoni ne opsionet e meposhtme:




Do te hapet folderi i meposhtem ku ju duhet te hapni folderin ext:



dll file te bere download ne hapin me larte bejeni drag and drop ne folderin ext:




Zgjedhni opsionin si me poshte:




Gjejeni pjesen e Module Settings dhe shkruani extension=php_sqlsrv.dll:

```
;;;;;;;;;;;;;;;;;;;
; Module Settings ;
;;;;;;;;;;;;;;;;;;;
asp_tags=Off
display_startup_errors=On
track_errors=Off
y2k_compliance=On
allow_call_time_pass_reference=Off
safe_mode=Off
safe_mode_gid=Off
safe_mode_allowed_env_vars=PHP_
safe_mode_protected_env_vars=LD_LIBRARY_PATH
error_log="C:\xampp\php\logs\php_error_log"
register_globals=Off
register_long_arrays=Off
magic_quotes_gpc=Off
magic_quotes_runtime=Off
magic_quotes_sybase=Off
extension=php_openssl.dll
extension=php_ftp.dll
extension=php_sqlsrv.dll
```



Tani duhet te instalohet driver qe ben lidhjen ne mes te PHP dhe SQL Server, driver duhet te instalohet varesisht prej versionit te SQL Server qe ju keni te instaluar. Shkruani ne browser tekstin si me poshte varesisht prej versionit te SQL Server.



Te pjesa e Download zgjedhni njerin prej opsioneve:



Instaloni Setup duke klikuar vetem next dhe ne fund finish.