

Operator User Manual

Field	Value
Document ID	UAIL-ITDASH-OPS-001
Version	1.0
Status	Internal review
Classification	Internal
Owner	Tech-Unit IT
Last Updated	2026-07-17
Audience	Operators and wallboard viewers

1. Audience


This guide is for operations users who monitor the wallboard and use dashboard filters but do not manage services or credentials.

2. Login

Browse to the operator surface:

- `http://<server>:21060/login`

Use the operator password on the operator login page.



3. What You See

The operator wallboard is organized into:

- HCI cluster metrics
- Hindalco Service Desk metrics
- Network fabric metrics
- Server fleet metrics

4. Reading Data-Link Status

Every major card includes a compact data-link status area. Use it as follows:

- **OK** : source is updating normally
- **STALE** : last success is older than expected
- **ERROR** : collector attempted a refresh but failed
- **NEVER** : no successful sync yet

Important:

- the card continues to show the last successfully synced data when the source fails
- the timestamp indicates when the displayed values were last confirmed

5. Color Language

- Green: normal/healthy
- Amber: warning
- Orange: elevated concern
- Red: critical or about to miss
- Grey/slate: offline or unavailable

6. Filters

Use the filter bar to show or hide:

- sections: HCI, HSD, Network, Servers
- server status: normal, warning, critical, offline
- server platform: HCI VM, On Prem
- server OS: Windows, Linux
- server source: Nutanix, SW45, Fallback
- network carrier: Jio, RailTel, Other
- network path: ISP, SDWAN
- network state: Up, Warning, Down
- HSD work type: Incidents, Service Requests, Work Orders, Changes
- HSD special queues: P1, P2, Onboard, Security

7. How To Interpret Each Section

7.1 HCI

- Shows live cluster metrics from Nutanix
- Node chips show node state
- Utilization bars show quick threshold posture

7.2 HSD

- Big numbers represent current open workload totals
- Vertical breakdown charts show the status mix
- SLA widgets summarize current compliance posture
- P1, P2, onboarding, and security counts identify queue pressure

7.3 Network

- Link pills summarize carrier and SDWAN state
- Sparklines show real-time utilization trend
- Tx and Rx values show current bandwidth directionally

7.4 Servers

- Servers are organized by platform and OS family
- Color-coded bars summarize resource or health posture
- Fallback state indicates a Nutanix-backed server is temporarily shown from SolarWinds because Nutanix is stale

8. Mobile And Portrait View

On narrow screens the dashboard switches to a responsive stacked layout. This is intended for monitoring and quick inspection, not for replacing the main wallboard.

9. What Operators Should Do When Something Looks Wrong

- Check the card-level data-link status first
- If the card is stale or erroring, treat the values as last-synced, not current
- If the card is healthy but the metric is abnormal, treat it as a live condition
- Escalate session or service issues to an admin user

10. Logout

Use the logout control in the header when the operator session should end.