

# Volume & brightness: states & gestures

These two blanks aren't fills that drop a dead number. They're **live knobs**. This is every state they move through and every key that moves them. Shipped behaviour, verified live.

[Download PDF ↓](#)

[Download video ↓](#)

```
volume 26|
```

```
↳ 🔊 system volume    (ctrl+alt+up/down to adjust)
```

## volume

Labelled `system volume`. Each press moves it **6 percentage points**, between 0% and 100%.

Backed by `volume-blank.sh get|set` (Windows / macOS / PipeWire / PulseAudio / ALSA).

## brightness

Labelled `screen brightness`. Each press moves it **10 percentage points**, between 0% and 100%. Same script shape, same gestures, so everything here applies to both.

## Entry: how you get into a value

Include a number and it **sets** the level; leave it out and it just **reads** the current one. Either way you end up with the value in your text and the cursor on it.

| YOU TYPE              | MODE | YOUR TEXT BECOMES | WHAT HAPPENS                             |
|-----------------------|------|-------------------|------------------------------------------|
| volume _              | GET  | volume 26%        | reads the current level and writes it in |
| volume is _           | GET  | volume 26%        | a few words in between still work        |
| volume 40 _           | SET  | volume 40%        | turns the volume to 40%, writes it in    |
| set volume to 60<br>_ | SET  | volume 60%        | turns the volume to 60%                  |

The word `volume` stays in your text so the number still makes sense on its own later (`volume 40%`, not a stray `40%`).

## The note: what you see on the value

Standard `emoji · label · (hint)` format. The label persists (the standing "this is a live knob" signal); the one-time hint teaches the gesture, then drops after your first adjust.

### FIRST ENCOUNTER

```
volume 26%  
↳ 🔊 system volume (ctrl+alt+u)
```

Label + the teaching hint.

### AFTER YOUR FIRST ADJUST

```
volume 32%  
↳ 🔊 system volume
```

Hint gone, label stays: still visibly live.

# Gestures: what moves the value

Put the cursor on the number. Every press changes the real device and updates the number, never going below 0% or above 100%.


| KEY                     | DOES                                                      | AT THE EDGES                                                                     |
|-------------------------|-----------------------------------------------------------|----------------------------------------------------------------------------------|
| <code>Ctrl+Alt+↑</code> | raises it one step (6% for volume, 10% for brightness)    | stops at 100%                                                                    |
| <code>Ctrl+Alt+↓</code> | lowers it by the same step                                | stops at 0% (muted / screen dark)                                                |
| <code>_</code>          | <b>NEW</b> nudges it up one step, the quick one-key climb | climbs to 100% and stays there; the <code>_</code> is never typed into your text |

`_` is the one-direction quick nudge (up); use `Ctrl+Alt+↓` when you need to come back down. Both write straight to the device.

## The value states

One continuous 0–100 range with two special edges. The number in your text is the real value; the bars below are just to picture it.

NORMAL: ANYWHERE BETWEEN

32%  moves up or down a step at a time

76% 

TOP EDGE: 100%

100%  the maximum: pressing up again does nothing (it never wraps round to 0%)

volume 100%

🔊 system volume

BOTTOM EDGE: 0%

0%  silent / screen dark: pressing down again does nothing

```
volume 0%  
↳ 🔊 system volume
```

There is no "keep as is" and no countdown, because a dial has neither. It has a current value and directions. The clamp is felt, not labelled: the number simply stops moving at 0 and 100.

## Worked example: climbing with `_`

Verified live. `volume _` reads the current level (26%), then each bare `_` adds 6 points until it reaches 100% and stops.

Type `volume _`

reads 26%

```
volume 26%  
↳ 🔊 system volume (ctrl+alt+up/down)
```

Press `_`

$26 + 6 = 32\%$  · louder

```
volume 32%  
↳ 🔊 system volume
```

Press `_`

$32 + 6 = 38\%$

```
volume 38%  
↳ 🔊 system volume
```

Keep pressing `_`

at 98%, +6 would be 104%, so it stops at 100%

```
volume 100%  
↳ 🔊 system volume
```

Press `_` again

nothing changes, and no `_` is typed

```
volume 100%  
↳ 🔊 system volume
```

Press `Ctrl+Alt+↓`

$100 - 6 = 94\%$  · quieter

```
volume 94%  
↳ 🔊 system volume
```

It stops at the top, it does not wrap. Holding `_` down at 100% keeps it at 100%; it never rolls round to 0%. That is deliberate: one extra press should not silently mute you. To come back down, use `Ctrl+Alt+↓`.

---

Reflects shipped behaviour: `defaults/blanks/{volume,brightness}/BLANK.md` + `dim-render.ts` (note) + `cycling.ts` ( `cycleBlankStep`, caret-armed `step()`, `_`-nudge in `stepUnderscore` ). Verified live on OpenCode + Claude Code. Values write straight to the device via the blank's script; a host with no audio/brightness backend is a silent no-op.