

TicketsCAD — Command Bar Cheat Sheet

Press **/** anywhere to open it (not while typing in a field) · type a name or short prefix, **Enter** to run

DISPATCH & WORKFLOW

/new	–	Create a new incident
/incidents	/inc	Focus the Active Incidents widget
/responders	/res /resp	Focus the Responders widget
/units	/uni	Focus the Responders widget (units view)
/facilities	/fac	Focus the Facilities widget
/activity	/logs	Focus the Activity Log widget
/detail	–	Open detail page for the selected incident
/zello	/zel	Toggle the Zello radio panel
/road	–	Toggle the road-conditions overlay on the dashboard map
/radio	–	Open the radio (DMR) widget

NAVIGATION — JUMP TO A PAGE

/dashboard	/dash /home /sit /situ /situation	Open the dashboard (situational view)
/bigscreen	/wall /fullscreen /eoc	Open the full-screen situation display (large monitor)
/search	—	Open the search page
/reports	—	Open the reports page
/settings	—	Open the settings / configuration page
/sop	—	Open the SOP viewer
/help	—	Open the help page
/roster	—	Open the personnel roster
/teams	/team	Open the teams page
/schedule	—	Open the scheduling page
/vehicles	—	Open the vehicles page
/equipment	—	Open the equipment page
/roles	—	Open the roles & permissions admin page
/profile	—	Open your user profile
/contacts	/constituents	Open the contacts / constituents page
/messages	/messaging	Open internal messaging
/links	—	Open the external links page
/ics	/forms	Open the ICS forms page

/major /events Open the Major Event list

SETTINGS DEEP LINKS

/users	—	Settings → User Accounts
/audit	—	Settings → Audit Log
/types	—	Settings → Incident Types
/organizations	/orgs	Settings → Organizations
/password	—	Change your password
/training	—	Settings → Training
/zones	—	Settings → Alert Zones

UNIT STATUS — CHANGE A UNIT WITHOUT OPENING A MODAL

```
/s <handle> <status>
/status <handle> <status>      (same thing — /s and /st also work)
```

/s M21 av → Medic 21 → Available

/status E2 disp → Engine 2 → Dispatched

/s Engine 2 dispatched → Multi-word unit names work too

/s M4 out of service → Three-word statuses work too

The status keyword is read from the END of what you type, so everything before it is treated as the unit handle. Case doesn't matter. Statuses needing extra info (destination, reason) route you to the unit's S-key modal instead. An unrecognized word is still tried against your install's own configured statuses.

EVENT NET-CONTROL ZONE MOVE

```
/z <team> <zone>
```

/z alpha 3 → Team Alpha → the zone with code or name "3"

/z echo clear → Echo's zone assignment is cleared (clear, none, off all work)

Requires an active event selected on the Net Control board first.

NET-CONTROL CHECK-INS — CAPTURE A WHOLE ROUND IN ONE LINE

```
/net <id> <note> / <id> <note> / <id> <note> ...
```

/net 1234 tornado / 3344 hail → Two check-ins captured in one keystroke

First word of each entry is the identifier, the rest is the note. Separate entries with /. Opens the situational screen with the check-ins loaded.

QUICK NOTES — CAPTURE A NOTE FROM ANYWHERE

`/log <text>` → capture a timestamped note in one keystroke
`/log` → open the notes list to review/file it

`/log KOB reported at 4th and Main` → Note captured instantly, no navigation

Renamed from the Activity Log widget-focus command (that's `/activity` now) so this shorter name could go to quick capture instead.

UNIT STATUS SHORTCUTS

Available	av avail available
Busy	busy
Unavailable	unav unavail unavailable
Dispatched	disp dispatched dp
Enroute	en enr enroute
Responding	resp responding
On Scene	os onscene on-scene on_scene
Transporting	tx transp transport transporting
At Facility	af atfacility at-facility
In Quarters	iq inquarters in-quarters
Out of Service	oos

WHILE THE BAR IS OPEN

Enter	Run the command
Tab	Complete to highlighted suggestion
↑ / ↓	Move the highlight
Esc	Close, do nothing