

Step 3: create an AMI from EC2 Instance

- * To ensure Auto scaling creates identical instances, create an AMI from the EC2 instance
- * In the EC2 Dashboard, select your running instance.
- * choose Actions → Image and templates → create image.
- * Enter a name and description for the image and click create image.

Step 4: Set up an Auto Scaling Group.

- * Navigate to the Auto Scaling dashboard
- * In the AWS console, search for Auto scaling and open the auto scaling groups service.
- * Create a Launch Template:
- * A launch template is required to specify the instance configuration
- * click on launch templates → create Launch Template
- * Enter a name for the template
- * under launch template contents, configure the instance details based on your earlier EC2 setup.
- * create an Auto scaling group
- * After creating the launch template, navigate to Auto Scaling Groups → create Auto scaling group.

PROGRAM - 5

D D M M Y Y Y Y
□ □ □ □ □ □ □ □

conduct an experiment to establish an environment with automatic scaling.

Step 1: Set up an AWS Account

- * If you don't have an AWS account, sign up at aws.amazon.com. After registering, sign in to the AWS Management console.

Step 2: Launch an Amazon EC2 Instance

- * Navigate to the EC2 Dashboard:
- * Search for EC2 in the AWS Management console and open the EC2 service.
- * Launch a new instance:
- * Click Launch instance:
- * Choose an Amazon Machine Image (AMI) for example, Amazon Linux 2.
- * Select an instance type (e.g., t2.micro for free-tier usage).
- * Configure Instance Details including network settings.
- * In the storage settings, you can leave the defaults.
- * In Security Groups, configure inbound rules for required protocols.
- * Review and click Launch.

- * Select the previously created launch template
- * Specify the Group name and VPC/subnets for the scaling group.
- * Configure Group size and scaling policies.
- * Set the desired capacity (initial number of instances), minimum size, and maximum size.
 - * E.g., minimum=1, desired=2, maximum=4.
- * Select Scaling Policies.
- * Choose Target Tracking to automatically scale based on CPU utilization or another metric.
 - * For example, you can set a target to maintain CPU utilization at 50%.
- * Configure Load Balancing (optional)
- * If you have a load balancer, attach it to distribute traffic across multiple instances.
- * Ensure the health check is enabled for the instances
- * Review and create.
- * Review all settings and click create Auto scaling group.