








STM32CubeMX Desktop: STM32F103C8Tx

File Window Help myST

Home > STM32F103C8Tx > Desktop: Pinout & Configuration

GENERATE CODE

Pinout & Configuration Clock Configuration Project Manager Tools

Software Packs Pinout

Categories A-Z

System Core >

Analog >

Timers >

RTC

TIM1

TIM2

TIM3

TIM4

Connectivity >

Computing >

Middleware and Software Packs >

Mode

Slave Mode: Disable

Trigger Source: Disable

☒ Internal Clock

Channel1: Disable

Channel2: Disable

Channel3: Disable

Channel4: Disable

Combined Channels: Disable

☐ XOR activation

☐ One Pulse Mode

Configuration

Reset Configuration

Parameter Settings User Constants NVIC Settings DMA Settings

Configure the below parameters:

Search (Ctrl+F)

Counter Settings

Prescaler (PSC - 16 bits value): 7199

Counter Mode: Up

Counter Period (AutoReload Register - 4999)

Internal Clock Division (CKD): No Division

auto-reload preload: Disable

Trigger Output (TRGO) Parameters

Master/Slave Mode (MSM) bit: Disable (Triggers input effect not released)

Pinout view System view

STM32CubeMX Desktop: STM32F103C8Tx

File Window Help myST

Home > STM32F103C8Tx > Desktop: Pinout & Configuration

GENERATE CODE

Pinout & Configuration Clock Configuration Project Manager Tools

Software Packs Pinout

Categories A-Z

System Core >

DMA

GPIO

IWDG

NVIC

☒ RCC

☒ SYS

WWDG

Analog >

Timers >

Connectivity >

CAN

☒ I2C1

☒ I2C2

SPI1

SPI2

USART1

USART2

USART3

☒ USB

Comms >

GPIO Mode and Configuration

Group By Peripherals

☒ GPIO ☒ I2C ☒ RCC ☒ USB

Search Signals

Search (Ctrl+F)

☐ Show only Modified Pins

Pin No.	Signal on	GPIO outp.	GPIO mode	GPIO Pull-up	Maximum	User Label	Modified
PA0-WK...	n/a	n/a	Input mode	Pull-up	n/a	SW_MENU	☒
PA1	n/a	n/a	Input mode	Pull-up	n/a	SW_UP	☒
PA2	n/a	n/a	Input mode	No pull-up	n/a	SW_DO...	☒
PA3	n/a	Low	Output Pu...	No pull-up	Low	FAN_CTRL	☒
PA4	n/a	Low	Output Pu...	No pull-up	Low	LED1_O...	☒
PA5	n/a	Low	Output Pu...	No pull-up	Low	LED2_O...	☒

PA2 Configuration:

GPIO mode: Input mode

GPIO Pull-up/Pull-down: No pull-up and no pull-down

User Label: Pull-up

GPIO Pull-up: GPIO_PULLUP

Pinout view System view

STM32CubeMX Desktop.ioct; STM32F103C8Tx

File Window Help myST

Home > STM32F103C8Tx > Desktop.ioct - Pinout & Configuration > GENERATE CODE

Pinout & Configuration Clock Configuration Project Manager Tools

Software Packs Pinout

Pinout view System view

Categories A-Z

- DMA
- GPIO
- IWDG
- NVIC
- ✓ RCC
- ▲ SYS
- WWDG

Analog >

Timers

- RTC
- ▲ TIM1
- ▲ TIM2
- ✓ TIM3
- TIM4

Connectivity

- CAN
- IC1
- ✓ I2C2
- SPI1
- SPI2
- USART1
- USART2
- USART3

TIM3 Mode and Configuration

Mode

Slave Mode [Disable]

Trigger Source [Disable]

☒ Internal Clock

Channel1 [Disable]

Channel2 [Disable]

Channel3 [Disable]

Channel4 [Disable]

Combined Channels [Disable]

☐ XOR activation

☐ One Pulse Mode

Configuration

Reset Configuration

● NVIC Settings ● DMA Settings

● Parameter Settings ● User Constants

NVIC Interrupt Table	Enabled	Presemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

STM32F103C8Tx LQFP48

Pinout view

System view

Pinout view

System view

